


Watcom Linker

User's Guide



Edition 11.0c

Notice of Copyright

Copyright © 2000 Sybase, Inc. and its subsidiaries. All rights reserved.

No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc. and its subsidiaries.

Printed in U.S.A.

Preface

The *Watcom Linker User's Guide* describes how to use the Watcom Linker under DOS, OS/2, Windows 95, Windows NT and QNX. The Watcom Linker can generate executable files that run under DOS, FlashTek's DOS extender, Phar Lap's 386DOS-Extender and TNT DOS extender, Tenberry Software's DOS/4G, Microsoft Windows 3.x, Microsoft Windows NT, Microsoft Windows 95, IBM OS/2, QNX, and Novell's NetWare 386 operating system. The Watcom Linker can also generate ELF format executable files for those systems that will support ELF. The Microsoft Response File conversion utility, MS2WLINK, is also described in this book.

Acknowledgements

This book was produced with the Watcom GML electronic publishing system, a software tool developed by WATCOM. In this system, writers use an ASCII text editor to create source files containing text annotated with tags. These tags label the structural elements of the document, such as chapters, sections, paragraphs, and lists. The Watcom GML software, which runs on a variety of operating systems, interprets the tags to format the text into a form such as you see here. Writers can produce output for a variety of printers, including laser printers, using separately specified layout directives for such things as font selection, column width and height, number of columns, etc. The result is type-set quality copy containing integrated text and graphics.

September, 2000.

Trademarks Used in this Manual

DOS/4G is a trademark of Tenberry Software, Inc.

OS/2 and Presentation Manager are trademarks of International Business Machines Corp. IBM, IBM PC and IBM PS/2 are registered trademarks of International Business Machines Corp.

Intel is a registered trademark of Intel Corp.

Microsoft, Windows and Windows 95 are registered trademarks of Microsoft Corp. Windows NT is a trademark of Microsoft Corp.

NetWare, NetWare 386, and Novell are registered trademarks of Novell, Inc.

Phar Lap, 386|DOS-Extender and TNT are trademarks of Phar Lap Software, Inc.

QNX is a registered trademark of QNX Software Systems Ltd.

WATCOM is a trademark of Sybase, Inc. and its subsidiaries.

Table of Contents

The WATCOM Linker	1
1 The Watcom Linker	3
2 Linking Executable Files for Various Systems	5
2.1 Using the SYSTEM Directive	5
2.2 Linking 16-bit x86 Executable Files	8
2.2.1 Linking 16-bit x86 DOS Executable Files	8
2.2.2 Linking 16-bit x86 DOS .COM Executable Files	8
2.2.3 Linking 16-bit x86 OS/2 Executable Files	9
2.2.4 Linking 16-bit x86 OS/2 Dynamic Link Libraries	9
2.2.5 Linking 16-bit x86 QNX Executable Files	9
2.2.6 Linking 16-bit x86 Windows 3.x Executable Files	10
2.2.7 Linking 16-bit x86 Windows 3.x Dynamic Link Libraries	10
2.3 Linking 32-bit x86 Executable Files	11
2.3.1 Linking 32-bit x86 AutoCAD Development System Executable Files	11
2.3.2 Linking 32-bit x86 AutoCAD Device Interface Executable Files	11
2.3.3 Linking 32-bit x86 DOS/4GW Executable Files	12
2.3.4 Linking 32-bit x86 FlashTek Executable Files	12
2.3.5 Linking 32-bit x86 Novell NetWare Loadable Modules	13
2.3.6 Linking 32-bit x86 OS/2 Executable Files	13
2.3.7 Linking 32-bit x86 OS/2 Dynamic Link Libraries	14
2.3.8 Linking 32-bit x86 OS/2 Presentation Manager Executable Files	14
2.3.9 Linking 32-bit x86 Phar Lap Executable Files	14
2.3.10 Linking 32-bit x86 Phar Lap TNT Executable Files	15
2.3.11 Linking 32-bit x86 QNX Executable Files	15
2.3.12 Linking 32-bit x86 Extended Windows 3.x Executable	15
2.3.13 Linking 32-bit x86 Extended Windows 3.x Dynamic Link Libraries	16
2.3.14 Linking 32-bit x86 Windows 95 Executable Files	16
2.3.15 Linking 32-bit x86 Windows 95 Dynamic Link Libraries	16
2.3.16 Linking 32-bit x86 Windows NT Character-Mode Executable Files	17
2.3.17 Linking 32-bit x86 Windows NT Windowed Executable Files ...	17
2.3.18 Linking 32-bit x86 Windows NT Dynamic Link Libraries	17
3 Linker Directives and Options	19
3.1 The ALIAS Directive	22
3.2 The ALIGNMENT Option	23

Table of Contents

3.3 The ANONYMOUSEXPORT Directive	24
3.4 The ARTIFICIAL Option	26
3.5 The CACHE Option	27
3.6 The CASEEXACT Option	28
3.7 The CHECK Option	29
3.8 The # Directive	30
3.9 The COMMIT Directive	31
3.10 The COPYRIGHT Option	32
3.11 The CUSTOM Option	33
3.12 The CVPACK Option	34
3.13 The DEBUG Directive	35
3.13.1 Line Numbering Information - DEBUG WATCOM LINES	37
3.13.2 Local Symbol Information - DEBUG WATCOM LOCALS	38
3.13.3 Typing Information - DEBUG WATCOM TYPES	38
3.13.4 All Debugging Information - DEBUG WATCOM ALL	39
3.13.5 Global Symbol Information	39
3.13.6 Global Symbols for the NetWare 386 Debugger - DEBUG NOVELL	39
3.13.7 The ONLYEXPORTS Debugging Option	40
3.13.8 Using DEBUG Directives	40
3.13.9 Removing Debugging Information from an Executable File	41
3.14 The DESCRIPTION Option	42
3.15 The DISABLE Directive	43
3.16 The DOSSEG Option	45
3.17 The ELIMINATE Option	47
3.18 The ENDLINK Directive	48
3.19 The EXIT Option	49
3.20 The EXPORT Directive	50
3.20.1 EXPORT - OS/2, Win16, Win32 only	50
3.20.2 EXPORT - ELF only	52
3.20.3 EXPORT - Netware only	53
3.21 The FILE Directive	54
3.22 The FORMAT Directive	56
3.23 The HEAPSIZ Option	64
3.24 The HELP Option	65
3.25 The IMPFILE Option	66
3.26 The IMPLIB Option	67
3.27 The IMPORT Directive	68
3.27.1 IMPORT - OS/2, Win16, Win32 only	68
3.27.2 IMPORT - ELF only	69
3.27.3 IMPORT - Netware only	69
3.28 The @ Directive	71

Table of Contents

3.29 The INCREMENTAL Option	74
3.30 The INTERNALRELOCS Option	76
3.31 The LANGUAGE Directive	77
3.32 The LIBFILE Directive	78
3.33 The LIBPATH Directive	80
3.34 The LIBRARY Directive	82
3.34.1 Searching for Libraries Specified in Environment Variables	83
3.34.2 Converting Libraries Created using Phar Lap 386 LIB	84
3.35 The LINEARRELOCS Option	85
3.36 The LONGLIVED Option	86
3.37 The MANGLEDNAMES Option	87
3.38 The MANYAUTODATA Option	88
3.39 The MAP Option	89
3.40 The MAXDATA Option	90
3.41 The MAXERRORS Option	91
3.42 The MESSAGES Option	92
3.43 The MINDATA Option	93
3.44 The MODNAME Option	94
3.45 The MODFILE Directive	95
3.46 The MODTRACE Directive	96
3.47 The MODULE Directive	97
3.48 The MULTILOAD Option	98
3.49 The NAME Directive	99
3.50 The NAMELEN Option	100
3.51 The NEWFILES Option	101
3.52 The NEWSEGMENT Directive	102
3.53 The NLMFLAGS Option	103
3.54 The NOAUTODATA Option	104
3.55 The NODEFAULTLIBS Option	105
3.56 The NORELOCS Option	106
3.57 The NOSTDCALL Option	107
3.58 The OBJALIGN Option	108
3.59 The OLDLIBRARY Option	109
3.60 The OFFSET Option	110
3.60.1 OFFSET - OS/2, Win32 only	110
3.60.2 OFFSET - PharLap only	111
3.60.3 OFFSET - QNX only	111
3.61 The ONEAUTODATA Option	113
3.62 The OPTION Directive	114
3.63 The OPTLIB Directive	115
3.63.1 Searching for Optional Libraries Specified in Environment Variables	116

Table of Contents

3.64 The OSDOMAIN Option	117
3.65 The PSEUDOPREEMPTION Option	118
3.66 The OSNAME Option	119
3.67 The PACKCODE Option	120
3.68 The PACKDATA Option	121
3.69 The PATH Directive	122
3.70 The PRIVILEGE Option	124
3.71 The PROTMODE Option	125
3.72 The QUIET Option	126
3.73 The REDEFSOK Option	127
3.74 The REENTRANT Option	128
3.75 The REFERENCE Directive	129
3.76 The RESOURCE Option	130
3.76.1 RESOURCE - OS/2, Win16, Win32 only	130
3.76.2 RESOURCE - QNX only	130
3.77 The RUNTIME Directive	132
3.77.1 RUNTIME - Win32 only	132
3.77.2 RUNTIME - PharLap only	133
3.78 The RWRELOCHECK Option	136
3.79 The SCREENNAME Option	137
3.80 The SEGMENT Directive	138
3.81 The SHARELIB Option	141
3.82 The SHOWDEAD Option	142
3.83 The SORT Directive	143
3.84 The STACK Option	144
3.85 The START Option	145
3.86 The STARTLINK Directive	146
3.87 The STATICS Option	147
3.88 The STUB Option	148
3.89 The SYMFILE Option	149
3.90 The SYMTRACE Directive	151
3.91 The SYNCHRONIZE Option	152
3.92 The SYSTEM Directive	153
3.92.1 Special System Names	156
3.93 The THREADNAME Option	157
3.94 The TOGGLERELOCS Option	158
3.95 The UNDEFSOK Option	159
3.96 The VERBOSE Option	160
3.97 The VERSION Option	161
3.98 The VFREMOVAL Option	162
3.99 The XDCDATA Option	163

Table of Contents

4 The DOS Executable File Format	165
4.1 Memory Layout	167
4.2 The Watcom Linker Memory Requirements	168
4.3 Using Overlays	168
4.4 Converting Microsoft Response Files to Directive Files	168
5 The ELF Executable File Format	171
5.1 Memory Layout	173
5.2 The Watcom Linker Memory Requirements	174
6 The NetWare 386 Executable File Format	175
6.1 NetWare Loadable Modules	177
6.2 Memory Layout	178
6.3 The Watcom Linker Memory Requirements	179
7 The OS/2 Executable and DLL File Formats	181
7.1 Dynamic Link Libraries	184
7.1.1 Creating a Dynamic Link Library	184
7.1.2 Using a Dynamic Link Library	185
7.2 Memory Layout	185
7.3 The Watcom Linker Memory Requirements	186
7.4 Converting Microsoft Response Files to Directive Files	187
8 The Phar Lap Executable File Format	189
8.1 32-bit Protected-Mode Applications	191
8.2 Memory Usage	191
8.3 Memory Layout	192
8.4 The Watcom Linker Memory Requirements	193
9 The QNX Executable File Format	195
9.1 Memory Layout	197
9.2 The Watcom Linker Memory Requirements	198
10 The Win16 Executable and DLL File Formats	199
10.1 Fixed and Moveable Segments	201
10.2 Discardable Segments	202
10.3 Dynamic Link Libraries	202
10.3.1 Creating a Dynamic Link Library	203
10.3.2 Using a Dynamic Link Library	204
10.4 Memory Layout	204
10.5 The Watcom Linker Memory Requirements	205
10.6 Converting Microsoft Response Files to Directive Files	205

Table of Contents

11 The Win32 Executable and DLL File Formats	207
11.1 Dynamic Link Libraries	209
11.1.1 Creating a Dynamic Link Library	210
11.1.2 Using a Dynamic Link Library	211
11.2 Memory Layout	211
11.3 The Watcom Linker Memory Requirements	212
12 Watcom Linker Diagnostic Messages	213

The WATCOM Linker

1 *The Watcom Linker*

The Watcom Linker is a linkage editor (linker) that takes object and library files as input and produces executable files as output. The following object module and library formats are supported by the Watcom Linker.

- The standard Intel Object Module Format (OMF).
- Microsoft's extensions to the standard Intel OMF.
- Phar Lap's Easy OMF-386 object module format for linking 386 applications.
- The COFF object module format.
- The ELF object module format.
- The OMF library format.
- The AR (Microsoft compatible) object library format.

The Watcom Linker is capable of producing a number of executable file formats. The following lists these executable file formats.

- DOS executable files
- ELF executable files
- executable files that run under FlashTek's DOS extender
- executable files that run under Phar Lap's 386DOS-Extender
- executable files that run under Tenberry Software's DOS/4G and DOS/4GW DOS extenders
- executable files that run under Autodesk's AutoCAD Development System
- NetWare Loadable Modules (NLMs) that run under Novell's NetWare 386 operating system

- OS/2 executable files including Dynamic Link Libraries
- QNX executable files
- 16-bit Windows (Win16) executable files including Dynamic Link Libraries
- 32-bit Windows (Win32) executable files including Dynamic Link Libraries

In addition to being able to generate the above executable file formats, the Watcom Linker also runs under a variety of operating systems. Currently, the Watcom Linker runs under the following operating systems.

- DOS
- OS/2
- QNX
- Windows NT
- Windows 95

We refer to the operating system upon which you run the Watcom Linker as the "host".

The chapter entitled "Linking Executable Files for Various Systems" on page 5 summarizes each of the executable file formats that can be generated by the linker. The chapter entitled "Linker Directives and Options" on page 19 describes all of the linker directives and options. The remaining chapters describe aspects of each of the executable file formats.

2 Linking Executable Files for Various Systems

The Watcom Linker command line format is as follows.

```
wlink {directive}
```

where *directive* is a series of Watcom Linker directives specified on the command line or in one or more files. If the directives are contained within a file, the "@" character is used to reference that file. If no file extension is specified, a file extension of ".lnk" is assumed.

Example:

```
wlink name testprog @first @second option map
```

In the above example, directives are specified on the command line (e.g., "name testprog" and "option map") and in files (e.g., FIRST.LNK and SECOND.LNK).

2.1 Using the SYSTEM Directive

For each executable file format that can be created using the Watcom Linker, a specific SYSTEM directive may be used. The SYSTEM directive selects a subset of the available directives necessary to create each specific executable file format.

<i>System</i>	<i>Description</i>
<i>com</i>	16-bit x86 DOS ".COM" executable
<i>dos</i>	16-bit x86 DOS executable
<i>dos4g</i>	32-bit x86 DOS/4GW executable
<i>dos4gnz</i>	non-zero based 32-bit x86 DOS/4GW executable

<i>netware</i>	32-bit x86 NetWare Loadable Module
<i>novell</i>	synonym for "netware"
<i>os2</i>	16-bit x86 OS/2 executable
<i>os2 dll</i>	16-bit x86 OS/2 Dynamic Link Library
<i>os2v2</i>	32-bit x86 OS/2 executable
<i>os2v2 dll</i>	32-bit x86 OS/2 Dynamic Link Library
<i>os2v2_pm</i>	32-bit x86 OS/2 Presentation Manager executable
<i>pharlap</i>	32-bit x86 Phar Lap executable
<i>tnt</i>	32-bit x86 Phar Lap TNT executable
<i>qnx</i>	16-bit x86 QNX executable
<i>qnx386</i>	32-bit x86 QNX executable
<i>x32r</i>	32-bit x86 FlashTek executable using register-based calling conventions
<i>x32rv</i>	32-bit x86 virtual-memory FlashTek executable using register-based calling conventions
<i>x32s</i>	32-bit x86 FlashTek executable using stack-based calling conventions
<i>x32sv</i>	32-bit x86 virtual-memory FlashTek executable using stack-based calling conventions
<i>windows</i>	16-bit x86 Windows 3.x executable
<i>windows_dll</i>	16-bit x86 Windows 3.x Dynamic Link Library
<i>win95</i>	32-bit x86 Windows 95 executable
<i>win95 dll</i>	32-bit x86 Windows 95 Dynamic Link Library
<i>nt</i>	32-bit x86 Windows NT character-mode executable
<i>nt_win</i>	32-bit x86 Windows NT windowed executable

6 Using the *SYSTEM* Directive

<i>win32</i>	synonym for "nt_win"
<i>nt_dll</i>	32-bit x86 Windows NT Dynamic Link Library
<i>win386</i>	32-bit x86 Watcom extended Windows 3.x executable or Dynamic Link Library
<i>ads</i>	32-bit x86 AutoCAD Development System executable
<i>eadi</i>	32-bit x86 Emulation AutoCAD Device Interface
<i>fadi</i>	32-bit x86 Floating-point AutoCAD Device Interface

The various systems that we have listed above are defined in special linker directive files which are plain ASCII text files that you can edit. These files are called `WLINK.LNK` and `WLSYSTEM.LNK`.

The file `WLINK.LNK` is a special linker directive file that is automatically processed by the Watcom Linker before processing any other directives. On a DOS, OS/2, or Windows-hosted system, this file must be located in one of the paths specified in the **PATH** environment variable. On a QNX-hosted system, this file should be located in the `/etc` directory. A default version of this file is located in the `\WATCOM\BINW` directory on DOS-hosted systems, the `\WATCOM\BINP` directory on OS/2-hosted systems, the `/etc` directory on QNX-hosted systems, and the `\WATCOM\BINNT` directory on Windows 95 or Windows NT-hosted systems. Note that the file `WLINK.LNK` includes the file `WLSYSTEM.LNK` which is located in the `\WATCOM\BINW` directory on DOS, OS/2, or Windows-hosted systems and the `/etc` directory on QNX-hosted systems.

The files `WLINK.LNK` and `WLSYSTEM.LNK` reference the **WATCOM** environment variable which must be set to the directory in which you installed your software.

In the following sections, we show some of the typical directives that you might use to create a particular executable file format. The common directives are described in the chapter entitled "Linker Directives and Options" on page 19. They are "common" in the sense that they may be used with any executable format. There are other, less general, directives that may be specified for a particular executable format. In each of the following sections, we refer you to chapters in which you will find more information on the directives available with the executable format used.

At this point, it should be noted that various systems have adopted particular executable file formats. For example, AutoCAD applications use a Phar Lap executable file format and both the Tenberry Software DOS/4G(W) and FlashTek DOS extenders support one of the OS/2 executable file formats. It is for this reason that you may find that we direct you to a chapter which would, at first glance, seem unrelated to the executable file format in which you are interested.

To summarize, the steps that you should follow to learn about creating a particular executable are:

1. Look for a section in this chapter that describes the executable format in which you are interested.
2. See the chapter entitled "Linker Directives and Options" on page 19 for a description of the common directives.
3. If you require additional information, see also the chapter to which we have referred you.
4. Also check the *Watcom C/C++ Programmer's Guide* or *Watcom FORTRAN 77 Programmer's Guide* for more information on creating specific types of applications.

2.2 Linking 16-bit x86 Executable Files

The following sections describe how to link a variety of 16-bit executable files.

2.2.1 Linking 16-bit x86 DOS Executable Files

To create this type of file, use the following structure.

```
system    dos
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The DOS Executable File Format" on page 165.

2.2.2 Linking 16-bit x86 DOS .COM Executable Files

To create this type of file, use the following structure.

8 Linking 16-bit x86 Executable Files

```
system    com
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The DOS Executable File Format" on page 165.

2.2.3 Linking 16-bit x86 OS/2 Executable Files

To create this type of file, use the following structure.

```
system    os2
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The OS/2 Executable and DLL File Formats" on page 181.

2.2.4 Linking 16-bit x86 OS/2 Dynamic Link Libraries

To create this type of file, use the following structure.

```
system    os2 dll
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The OS/2 Executable and DLL File Formats" on page 181.

2.2.5 Linking 16-bit x86 QNX Executable Files

To create this type of file, use the following structure.

```
system    qnx
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The QNX Executable File Format" on page 195.

2.2.6 Linking 16-bit x86 Windows 3.x Executable Files

To create this type of file, use the following structure.

```
system    windows
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The Win16 Executable and DLL File Formats" on page 199.

2.2.7 Linking 16-bit x86 Windows 3.x Dynamic Link Libraries

To create this type of file, use the following structure.

```
system    windows_dll
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The Win16 Executable and DLL File Formats" on page 199.

2.3 Linking 32-bit x86 Executable Files

The following sections describe how to create a variety of 32-bit executable files.

2.3.1 Linking 32-bit x86 AutoCAD Development System Executable Files

To create this type of file, use the following structure.

```
system    ads
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The Phar Lap Executable File Format" on page 189.

2.3.2 Linking 32-bit x86 AutoCAD Device Interface Executable Files

To create this type of file, use the following structure for an emulation AutoCAD Device Interface.

```
system    eadi
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

To create a floating-point AutoCAD Device Interface, specify

```
system    fadi.
```

For more information, see the chapter entitled "The Phar Lap Executable File Format" on page 189.

2.3.3 Linking 32-bit x86 DOS/4GW Executable Files

To create this type of file, use the following structure.

```
system  dos4g
option  map
name    app_name
file    obj1, obj2, ...
library lib1, lib2, ...
```

For more information, see the chapter entitled "The OS/2 Executable and DLL File Formats" on page 181.

2.3.4 Linking 32-bit x86 FlashTek Executable Files

To create these files, use one of the following structures.

```
system  x32r
option  map
name    app_name
file    obj1, obj2, ...
library lib1, lib2, ...
```

If the system is **x32r**, a FlashTek executable file is created for an application using the register calling convention.

```
system  x32rv
option  map
name    app_name
file    obj1, obj2, ...
library lib1, lib2, ...
```

If the system is **x32rv**, a virtual-memory FlashTek executable file is created for an application using the register calling convention.

```
system  x32s
option  map
name    app_name
file    obj1, obj2, ...
library lib1, lib2, ...
```

If the system is **x32s**, a FlashTek executable file is created for an application using the stack calling convention.

12 Linking 32-bit x86 Executable Files

```
system    x32sv
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

If the system is **x32sv**, a virtual-memory FlashTek executable file is created for an application using the stack calling convention.

For more information, see the chapter entitled "The OS/2 Executable and DLL File Formats" on page 181.

2.3.5 Linking 32-bit x86 Novell NetWare Loadable Modules

To create this type of file, use the following structure.

```
system    netware
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
module    mod_name
import    @%WATCOM%\novi\mod_name.imp
```

For more information, see the chapter entitled "The NetWare 386 Executable File Format" on page 175.

2.3.6 Linking 32-bit x86 OS/2 Executable Files

To create this type of file, use the following structure.

```
system    os2v2
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The OS/2 Executable and DLL File Formats" on page 181.

2.3.7 Linking 32-bit x86 OS/2 Dynamic Link Libraries

To create this type of file, use the following structure.

```
system  os2v2 dll
option  map
name    app_name
file    obj1, obj2, ...
library lib1, lib2, ...
```

For more information, see the chapter entitled "The OS/2 Executable and DLL File Formats" on page 181.

2.3.8 Linking 32-bit x86 OS/2 Presentation Manager Executable Files

To create this type of file, use the following structure.

```
system  os2v2_pm
option  map
name    app_name
file    obj1, obj2, ...
library lib1, lib2, ...
```

For more information, see the chapter entitled "The OS/2 Executable and DLL File Formats" on page 181.

2.3.9 Linking 32-bit x86 Phar Lap Executable Files

To create this type of file, use the following structure.

```
system  pharlap
option  map
name    app_name
file    obj1, obj2, ...
library lib1, lib2, ...
```

For more information, see the chapter entitled "The Phar Lap Executable File Format" on page 189.

2.3.10 Linking 32-bit x86 Phar Lap TNT Executable Files

To create this type of file, use the following structure.

```
system    tnt
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The Win32 Executable and DLL File Formats" on page 207.

2.3.11 Linking 32-bit x86 QNX Executable Files

To create this type of file, use the following structure.

```
system    qnx386
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The QNX Executable File Format" on page 195.

2.3.12 Linking 32-bit x86 Extended Windows 3.x Executable

To create this type of file, use the following structure.

```
system    win386
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

After linking this executable, you must bind the Watcom 32-bit Windows-extender to the executable (a .REX file) to produce a Windows executable (a .EXE file).

```
wbind -n app_name
```

For more information, see the chapter entitled "The Win16 Executable and DLL File Formats" on page 199.

2.3.13 Linking 32-bit x86 Extended Windows 3.x Dynamic Link Libraries

To create this type of file, use the following structure.

```
system    win386
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

After linking this executable, you must bind the Watcom 32-bit Windows-extender for DLLs to the executable (a .REX file) to produce a Windows Dynamic Link Library (a .DLL file).

```
wbind -n -d app_name
```

For more information, see the chapter entitled "The Win16 Executable and DLL File Formats" on page 199.

2.3.14 Linking 32-bit x86 Windows 95 Executable Files

To create this type of file, use the following structure.

```
system    win95
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The Win32 Executable and DLL File Formats" on page 207.

2.3.15 Linking 32-bit x86 Windows 95 Dynamic Link Libraries

To create this type of file, use the following structure.

```
system    win95 dll
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The Win32 Executable and DLL File Formats" on page 207.

2.3.16 Linking 32-bit x86 Windows NT Character-Mode Executable Files

To create this type of file, use the following structure.

```
system    nt
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The Win32 Executable and DLL File Formats" on page 207.

2.3.17 Linking 32-bit x86 Windows NT Windowed Executable Files

To create this type of file, use the following structure.

```
system    nt_win
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The Win32 Executable and DLL File Formats" on page 207.

2.3.18 Linking 32-bit x86 Windows NT Dynamic Link Libraries

To create this type of file, use the following structure.

```
system    nt_dll
option    map
name      app_name
file      obj1, obj2, ...
library   lib1, lib2, ...
```

For more information, see the chapter entitled "The Win32 Executable and DLL File Formats" on page 207.

3 *Linker Directives and Options*

The Watcom Linker supports a large set of directives and options. The following sections present these directives and options in alphabetical order. Not all directives and options are supported for all executable formats. When a directive or option applies only to a subset of the executable formats that the linker can generate, the supporting formats are noted. In the following example, the notation indicates that the directive or option is supported for all executable formats.

Example:

```
Formats: All
```

In the following example, the notation indicates that the directive or option is supported for OS/2, 16-bit Windows and 32-bit Windows executable formats only.

Example:

```
Formats: OS/2, Win16, Win32
```

Directives tell the Watcom Linker how to create your program. For example, using directives you can tell the Watcom Linker which object files are to be included in the program, which library files to search to resolve undefined references, and the name of the executable file.

The file `WLINK.LNK` is a special linker directive file that is automatically processed by the Watcom Linker before processing any other directives. On a DOS, OS/2, or Windows-hosted system, this file must be located in one of the paths specified in the **PATH** environment variable. On a QNX-hosted system, this file should be located in the `/etc` directory. A default version of this file is located in the `\WATCOM\BINW` directory on DOS-hosted systems, the `\WATCOM\BINP` directory on OS/2-hosted systems, the `/etc` directory on QNX-hosted systems, and the `\WATCOM\BINNT` directory on Windows 95 or Windows NT-hosted systems. Note that the file `WLINK.LNK` includes the file `WLSYSTEM.LNK` which is located in the `\WATCOM\BINW` directory on DOS, OS/2, or Windows-hosted systems and the `/etc` directory on QNX-hosted systems.

The files `WLINK.LNK` and `WLSYSTEM.LNK` reference the **WATCOM** environment variable which must be set to the directory in which you installed your software.

It is also possible to use environment variables when specifying a directive. For example, if the **LIBDIR** environment variable is defined as follows,

```
set libdir=\test
```

then the linker directive

```
library %libdir%\mylib
```

is equivalent to the following linker directive.

```
library \test\mylib
```

Note that a space must precede a reference to an environment variable.

Many directives can take a list of one or more arguments separated by commas. Instead of a comma-delimited list, you can specify a space-separated list provided the list is enclosed in braces (e.g., { space delimited list }). For example, the "FILE" directive can take a list of object file names as an argument.

```
file first,second,third,fourth
```

The alternate way of specifying this is as follows.

```
file {first second third fourth}
```

Where this comes in handy is in make files, where a list of dependents is usually a space-delimited list.

```
OBJS = first second third fourth  
.  
.  
.  
wlink file {$(objs)}
```

The following notation is used to describe the syntax of linker directives and options.

- | | |
|---------------|--|
| ABC | All items in upper case are required. |
| [abc] | The item <i>abc</i> is optional. |
| {abc} | The item <i>abc</i> may be repeated zero or more times. |
| {abc}+ | The item <i>abc</i> may be repeated one or more times. |
| a b c | One of <i>a</i> , <i>b</i> or <i>c</i> may be specified. |

20 Linker Directives and Options

a ::= b The item *a* is defined in terms of *b*.

Certain characters have special meaning to the linker. When a special character must appear in a name, you can embed the string that makes up the name inside apostrophes (e.g., 'name@8'). This prevents the linker from interpreting the special character in its usual manner. This is also true for file or path names that contain spaces (e.g., 'program files\software\mylib'). Normally, the linker would interpret a space or blank in a file name as a separator. The special characters are listed below:

Character	Name of Character
	Blank
=	Equals
(Left Parenthesis
)	Right Parenthesis
,	Comma
.	Period
{	Left Brace
}	Right Brace
@	At Sign
#	Hash Mark
%	Percentage Symbol

3.1 The ALIAS Directive

Formats: All

The "ALIAS" directive is used to specify an equivalent name for a symbol name. The format of the "ALIAS" directive (short form "A") is as follows.

ALIAS alias_name=symbol_name{, alias_name=symbol_name}

where *description:*

alias_name is the alias name.

symbol_name is the symbol name to which the alias name is mapped.

Consider the following example.

```
alias sine=mysine
```

When the linker tries to resolve the reference to `sine`, it will immediately substitute the name `mysine` for `sine` and begin searching for the symbol `mysine`.

3.2 The ALIGNMENT Option

Formats: ELF, OS/2, Win16, Win32

The "ALIGNMENT" option specifies the alignment for segments in the executable file. The format of the "ALIGNMENT" option (short form "A") is as follows.

<i>OPTION ALIGNMENT=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

$$[0x]d\{d\}[k|m]$$

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n specifies the alignment for segments in the executable file and must be a power of 2.

In 16-bit applications, segments in the executable file are pointed to by a segment table. An entry in the segment table contains a 16-bit value which is a multiple of the alignment value. Together they form the offset of the segment from the start of the segment table. Note that the smaller the value of *n* the smaller the executable file.

By default, the Watcom Linker will automatically choose the smallest value of *n* possible. You need not specify this option unless you want padding between segments in the executable file.

3.3 The ANONYMOUSEXPORT Directive

Formats: Win16, Win32

The "ANONYMOUSEXPORT" directive is an alternative to the "EXPORT" directive described in "The EXPORT Directive" on page 50. The symbol associated with this name will not appear in either the resident or the non-resident names table. The entry point is, however, still available for ordinal linking.

The format of the "ANONYMOUSEXPORT" directive (short form "ANON") is as follows.

```

ANONYMOUSEXPORT export{,export}
or
ANONYMOUSEXPORT =lbc_file

export ::= entry_name[.ordinal][=internal_name]
    
```

where *description:*

entry_name is the name to be used by other applications to call the function.

ordinal is an ordinal value for the function. If the ordinal number is specified, other applications can reference the function by using this ordinal number.

internal_name is the actual name of the function and should only be specified if it differs from the entry name.

lbc_file is a file specification for the name of a librarian command file. If no file extension is specified, a file extension of "lbc" is assumed. The linker will process the librarian command file and look for commands to the librarian that are used to create import library entries. These commands have the following form.

```
++sym.dll_name[.[altsym].export_name][.ordinal]
```

where *description:*

sym is the name of a symbol in a Dynamic Link Library.

dll_name is the name of the Dynamic Link Library that defines *sym*.

altsym is the name of a symbol in a Dynamic Link Library. When omitted, the default symbol name is *sym*.

export_name is the name that an application that is linking to the Dynamic Link Library uses to reference *sym*. When omitted, the default export name is *sym*.

ordinal is the ordinal value that can be used to identify *sym* instead of using the name *export_name*.

All other librarian commands will be ignored.

Notes:

1. By default, the Watcom C and C++ compilers append an underscore ('_') to all function names. This should be considered when specifying *entry_name* and *internal_name* in an "ANONYMOUSEXPORT" directive.
2. If the name contains characters that are special to the linker then the name may be placed inside apostrophes (e.g., `anonymousexport 'myfunc@8'`).
3. The symbol associated with the entry name will not appear in either the resident or the non-resident names table. The entry point is, however, still available for ordinal linking. This directive is important when you wish to reduce the number of entries that are placed in the resident and non-resident names table.

3.4 The ARTIFICIAL Option

Formats: All

The "ARTIFICIAL" option should only be used if you are developing a Watcom C++ application. A Watcom C++ application contains many compiler-generated symbols. By default, the linker does not include these symbols in the map file. The "ARTIFICIAL" option can be used if you wish to include these compiler-generated symbols in the map file.

The format of the "ARTIFICIAL" option (short form "ART") is as follows.

<i>OPTION ARTIFICIAL</i>

3.5 The CACHE Option

Formats: All

The "CACHE" and "NOCACHE" options can be used to control caching of object and library files in memory by the linker. When neither the "CACHE" nor "NOCACHE" option is specified, the linker will only cache small libraries. Object files and large libraries are not cached. The "CACHE" and "NOCACHE" options can be used to alter this default behaviour. The "CACHE" option enables the caching of object files and large library files while the "NOCACHE" option disables all caching.

The format of the "CACHE" option (short form "CAC") is as follows.

<i>OPTION CACHE</i>

The format of the "NOCACHE" option (short form "NOCAC") is as follows.

<i>OPTION NOCACHE</i>

When linking large applications with many object files, caching object files will cause extensive use of memory by the linker. On virtual memory systems such as OS/2, Windows NT or Windows 95, this can cause extensive page file activity when real memory resources have been exhausted. This can degrade the performance of other tasks on your system. For this reason, the OS/2 and Windows-hosted versions of the linker do not perform object file caching by default. This does not imply that object file caching is not beneficial. If your system has lots of real memory or the linker is running as the only task on the machine, object file caching can certainly improve the performance of the linker.

On single-tasking environments such as DOS, the benefits of improved linker performance outweighs the memory demands associated with object file caching. For this reason, object file caching is performed by default on these systems. If the memory requirements of the linker exceed the amount of memory on your system, the "NOCACHE" option can be specified.

The QNX operating system is a multi-tasking real-time operating system. However, it is not a virtual memory system. Caching object files can consume large amounts of memory. This may prevent other tasks on the system from running, a problem that may be solved by using the "NOCACHE" option.

3.6 The CASEEXACT Option

Formats: All

The "CASEEXACT" option tells the Watcom Linker to respect case when resolving references to global symbols. That is, "ScanName" and "SCANNAME" represent two different symbols. By default, the linker is case insensitive; "ScanName" and "SCANNAME" represent the same symbol. The format of the "CASEEXACT" option (short form "C") is as follows.

<i>OPTION CASEEXACT</i>

If you have specified the "CASEEXACT" option in the default directive files `WLINK.LNK` or `WLSYSTEM.LNK`, it is possible to override this option by using the "NOCASEEXACT" option. The "NOCASEEXACT" option turns off case-sensitive linking. The format of the "NOCASEEXACT" option (short form "NOCASE") is as follows.

<i>OPTION NOCASEEXACT</i>

The file `WLINK.LNK` is a special linker directive file that is automatically processed by the Watcom Linker before processing any other directives. On a DOS, OS/2, or Windows-hosted system, this file must be located in one of the paths specified in the **PATH** environment variable. On a QNX-hosted system, this file should be located in the `/etc` directory. A default version of this file is located in the `\WATCOM\BINW` directory on DOS-hosted systems, the `\WATCOM\BINP` directory on OS/2-hosted systems, the `/etc` directory on QNX-hosted systems, and the `\WATCOM\BINNT` directory on Windows 95 or Windows NT-hosted systems. Note that the file `WLINK.LNK` includes the file `WLSYSTEM.LNK` which is located in the `\WATCOM\BINW` directory on DOS, OS/2, or Windows-hosted systems and the `/etc` directory on QNX-hosted systems.

The files `WLINK.LNK` and `WLSYSTEM.LNK` reference the **WATCOM** environment variable which must be set to the directory in which you installed your software.

3.7 The CHECK Option

Formats: NetWare

The "CHECK" option specifies the name of a procedure to execute before an NLM is unloaded. This procedure can, for example, inform the operator that the NLM is in use and prevent it from being unloaded.

The format of the "CHECK" option (short form "CH") is as follows.

<i>OPTION CHECK=</i> <i>symbol_name</i>

where *description:*

symbol_name specifies the name of a procedure to execute before the NLM is unloaded.

If the "CHECK" option is not specified, no check procedure will be called.

3.8 The # Directive

Formats: All

The "#" directive is used to mark the start of a comment. All text from the "#" character to the end of the line is considered a comment. The format of the "#" directive is as follows.

<i># comment</i>

where *description:*

comment is any sequence of characters.

The following directive file illustrates the use of comments.

```
file main, trigtest

# Use my own version of "sin" instead of the
# library version.

file mysin
library \math\trig
```

3.9 The COMMIT Directive

Formats: Win32

When the operating system allocates the stack and heap for an application, it does not actually allocate the whole stack and heap to the application when it is initially loaded. Instead, only a portion of the stack and heap are allocated or committed to the application. Any part of the stack and heap that is not committed will be committed on demand.

The format of the "COMMIT" directive (short form "COM") is as follows.

```
COMMIT mem_type
```

```
mem_type ::= STACK=n / HEAP=n
```

where *description:*

n represents a value. The complete form of *n* is the following.

$$[0x]d\{d\}[k|m]$$

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n represents the amount of stack or heap that is initially committed to the application. The short form for "STACK" is "ST" and the short form for "HEAP" is "H".

If you do not specify the "COMMIT HEAP" directive then a 4k heap is committed to the application.

If you do not specify the "COMMIT STACK" directive then the default size is the smaller of 64K or the size specified by the "STACK" option. See the section entitled "The STACK Option" on page 144 for more information on specifying a stack size.

3.10 The *COPYRIGHT* Option

Formats: NetWare

The "COPYRIGHT" option specifies copyright information that is placed in the executable file. The format of the "COPYRIGHT" option (short form "COPYR") is as follows.

<i>OPTION COPYRIGHT 'string'</i>

where *description:*

string specifies the copyright information.

3.11 The CUSTOM Option

Formats: NetWare

The format of the "CUSTOM" option (short form "CUST") is as follows.

<i>OPTION CUSTOM=file_name</i>

where *description:*

file_name specifies the file name of the custom data file.

The custom data file is placed into the executable file when the application is linked but is really not part of the program. When the application is loaded into memory, the information extracted from a custom data file is not loaded into memory. Instead, information is passed to the program (as arguments) which allows the access and processing of this information.

3.12 The CVPACK Option

Formats: All

This option is only meaningful when generating Microsoft Codeview debugging information. This option causes the linker to automatically run the Watcom Codeview 4 Symbolic Debugging Information Compactor, CVPACK, on the executable that it has created. This is necessary to get the Codeview debugging information into a state where the Microsoft Codeview debugger will accept it.

The format of the "CVPACK" option (short form "CVP") is as follows.

<i>OPTION CVPACK</i>

For more information on generating Codeview debugging information into the executable, see the section entitled "The DEBUG Directive" on page 35

3.13 The *DEBUG* Directive

Formats: All

The "DEBUG" directive is used to tell the Watcom Linker to generate debugging information in the executable file. This extra information in the executable file is used by the Watcom Debugger. The format of the "DEBUG" directive (short form "D") is as follows.

```

DEBUG dbtype [dblist] /
DEBUG [dblist]

db_type ::= DWARF / WATCOM / CODEVIEW / NOVELL
db_list ::= [db_option{db_option}]
db_option ::= LINES / TYPES / LOCALS / ALL

DEBUG NOVELL only
db_option ::= ONLYEXPORTS / REFERENCED

```

The Watcom Linker supports four types of debugging information, "DWARF" (the default), "WATCOM", "CODEVIEW", or "NOVELL".

DWARF (short form "D") specifies that all object files contain Dwarf format debugging information and that the executable file will contain Dwarf debugging information.

This debugging format is assumed by default when none is specified.

WATCOM (short form "W") specifies that all object files contain WATCOM format debugging information and that the executable file will contain WATCOM debugging information. This format permits the selection of specific classes of debugging information (*db_list*) which are described below.

CODEVIEW

(short form "C") specifies that all object files contain Codeview (CV4) format debugging information and that the executable file will contain Codeview debugging information.

It will be necessary to run the Microsoft Debugging Information Compactor, CVPACK, on the executable that it has created. For information on requesting the linker to automatically run CVPACK, see the section entitled "The

CVPACK Option" on page 34 Alternatively, you can run CVPACK from the command line.

NOVELL (short form "N") specifies a form of global symbol information that can only be processed by the NetWare 386 debugger.

For the WATCOM debugging information format, we can be selective about the types of debugging information that we include with the executable file. We can categorize the types of debugging information as follows:

- global symbol information
- line numbering information
- local symbol information
- typing information
- NetWare 386 global symbol information

The following options can be used with the "DEBUG WATCOM" directive to control which of the above classes of debugging information is included in the executable file.

LINES (short form "LI") specifies line numbering and global symbol information.

LOCALS (short form "LO") specifies local and global symbol information.

TYPES (short form "T") specifies typing and global symbol information.

ALL (short form "A") specifies all of the above debugging information.

ONLYEXPORTS

(short form "ONL") restricts the generation of global symbol information to exported symbols. This option may only be used with Netware executable formats.

The following options can be used with the "DEBUG NOVELL" directive to control which of the above classes of debugging information is included in the executable file.

ONLYEXPORTS

(short form "ONL") restricts the generation of global symbol information to exported symbols.

REFERENCED

(short form "REF") restricts the generation of symbol information to referenced symbols only.

Note: The position of the "DEBUG" directive is important. The level of debugging information specified in a "DEBUG" directive only applies to object files and libraries that appear in *subsequent* "FILE" or "LIBRARY" directives. For example, if "DEBUG WATCOM ALL" was the only "DEBUG" directive specified and was also the last linker directive, no debugging information would appear in the executable file.

Only global symbol information is actually produced by the Watcom Linker; the other three classes of debugging information are extracted from object modules and copied to the executable file. Therefore, at compile time, you must instruct the compiler to generate local symbol, line numbering and typing information in the object file so that the information can be transferred to the executable file. If you have asked the Watcom Linker to produce a particular class of debugging information and it appears that none is present, one of the following conditions may exist.

1. The debugging information is not present in the object files.
2. The "DEBUG" directive has been misplaced.

The following sections describe the classes of debugging information.

3.13.1 Line Numbering Information - DEBUG WATCOM LINES

The "DEBUG WATCOM LINES" option controls the processing of line numbering information. Line numbering information is the line number and address of the generated code for each line of source code in a particular module. This allows Watcom Debugger to perform source-level debugging. When the Watcom Linker encounters a "DEBUG WATCOM" directive with a "LINES" or "ALL" option, line number information for each subsequent object module will be placed in the executable file. This includes all object modules extracted from object files specified in subsequent "FILE" directives and object modules extracted from libraries specified in subsequent "LIBRARY" or "FILE" directives.

Note: All modules for which line numbering information is requested must have been compiled with the "d1" or "d2" option.

A subsequent "DEBUG WATCOM" directive without a "LINES" or "ALL" option terminates the processing of line numbering information.

3.13.2 Local Symbol Information - *DEBUG WATCOM LOCALS*

The "DEBUG WATCOM LOCALS" option controls the processing of local symbol information. Local symbol information is the name and address of all symbols local to a particular module. This allows Watcom Debugger to locate these symbols so that you can reference local data and routines by name. When the Watcom Linker encounters a "DEBUG WATCOM" directive with a "LOCALS" or "ALL" option, local symbol information for each subsequent object module will be placed in the executable file. This includes all object modules extracted from object files specified in subsequent "FILE" directives and object modules extracted from libraries specified in subsequent "LIBRARY" or "FILE" directives.

Note: All modules for which local symbol information is requested must have been compiled with the "d2" option.

A subsequent "DEBUG WATCOM" directive without a "LOCALS" or "ALL" option terminates the processing of local symbol information.

3.13.3 Typing Information - *DEBUG WATCOM TYPES*

The "DEBUG WATCOM TYPES" option controls the processing of typing information. Typing information includes a description of all types, structures and arrays that are defined in a module. This allows Watcom Debugger to display variables according to their type. When the Watcom Linker encounters a "DEBUG WATCOM" directive with a "TYPES" or "ALL" option, typing information for each subsequent object module will be placed in the executable file. This includes all object modules extracted from object files specified in subsequent "FILE" directives and object modules extracted from libraries specified in subsequent "LIBRARY" or "FILE" directives.

Note: All modules for which typing information is requested must have been compiled with the "d2" option.

A subsequent "DEBUG WATCOM" directive without a "TYPES" or "ALL" option terminates the processing of typing information.

3.13.4 All Debugging Information - DEBUG WATCOM ALL

The "DEBUG WATCOM ALL" option specifies that "LINES", "LOCALS", and "TYPES" options are requested. The "LINES" option controls the processing of line numbering information. The "LOCALS" option controls the processing of local symbol information. The "TYPES" option controls the processing of typing information. Each of these options is described in a previous section. A subsequent "DEBUG WATCOM " directive without an "ALL" option discontinues those options which are not specified in the list of debug options.

3.13.5 Global Symbol Information

Global symbol information consists of all the global symbols in your program and their address. This allows Watcom Debugger to locate these symbols so that you can reference global data and routines by name. When the Watcom Linker encounters a "DEBUG" directive, global symbol information for all the global symbols appearing in your program is placed in the executable file.

3.13.6 Global Symbols for the NetWare 386 Debugger - DEBUG NOVELL

The NetWare 386 operating system has a built-in debugger that can be used to debug programs. When "DEBUG NOVELL" is specified, the Watcom Linker will generate global symbol information that can be used by the NetWare 386 debugger. Note that any line numbering, local symbol, and typing information generated in the executable file will not be recognized by the NetWare 386 debugger. Also, **WSTRIP** cannot be used to remove this form of global symbol information from the executable file.

3.13.7 The *ONLYEXPORTS* Debugging Option

The "ONLYEXPORTS" option (short form "ONL") restricts the generation of global symbol information to exported symbols (symbols appearing in an "EXPORT" directive). If "DEBUG WATCOM ONLYEXPORTS" is specified, Watcom Debugger global symbol information is generated only for exported symbols. If "DEBUG NOVELL ONLYEXPORTS" is specified, NetWare 386 global symbol information is generated only for exported symbols.

3.13.8 Using *DEBUG* Directives

Consider the following directive file.

```
debug watcom all
file module1
debug watcom lines
file module2, module3
debug watcom
library mylib
```

It specifies that the following debugging information is to be generated in the executable file.

1. global symbol information for your program
2. line numbering, typing and local symbol information for the following object files:

```
module1.obj
```

3. line numbering information for the following object files:

```
module2.obj
module3.obj
```

Note that if the "DEBUG WATCOM" directive before the "LIBRARY" directive is not specified, line numbering information for all object modules extracted from the library "mylib.lib" would be generated in the executable file provided the object modules extracted from the library have line numbering information present.

Note: A "DEBUG WATCOM" directive with no option suppresses the processing of line numbering, local symbol and typing information for all subsequent object modules.

Debugging information can use a significant amount of disk space. As shown in the above example, you can select only the class of debugging information you want and for those modules you wish to debug. In this way, the amount of debugging information in the executable file is minimized and hence the amount of disk space used by the executable file is kept to a minimum.

As you can see from the above example, the position of the "DEBUG WATCOM" directive is important when describing the debugging information that is to appear in the executable file.

Note: If you want all classes of debugging information for all files to appear in the executable file you must specify "DEBUG WATCOM ALL" before any "FILE" and "LIBRARY" directives.

3.13.9 Removing Debugging Information from an Executable File

A utility called **WSTRIP** has been provided which takes as input an executable file and removes the debugging information placed in the executable file by the Watcom Linker. Note that global symbol information generated using "DEBUG NOVELL" cannot be removed by **WSTRIP**.

For more information on this utility, see the chapter entitled "The Watcom Strip Utility" in the *Watcom C/C++ Tools User's Guide* or *Watcom FORTRAN 77 Tools User's Guide*.

3.14 The DESCRIPTION Option

Formats: OS/2, Win16, Win32

The "DESCRIPTION" option inserts the specified text into the application or Dynamic Link Library. This is useful if you wish to embed copyright information into an application or Dynamic Link Library. The format of the "DESCRIPTION" option (short form "DE") is as follows.

<i>OPTION DESCRIPTION 'string'</i>

where *description:*

string is the sequence of characters to be embedded into the application or Dynamic Link Library.

3.15 The *DISABLE* Directive

Formats: All

The "DISABLE" directive is used to disable the display of linker messages.

The Watcom Linker issues three classes of messages; fatal errors, errors and warnings. Each message has a 4-digit number associated with it. Fatal messages start with the digit 3, error messages start with the digit 2, and warning messages start with the digit 1. It is possible for a message to be issued as a warning or an error.

If a fatal error occurs, the linker will terminate immediately and no executable file will be generated.

If an error occurs, the linker will continue to execute so that all possible errors are issued. However, no executable file will be generated since these errors do not permit a proper executable file to be generated.

If a warning occurs, the linker will continue to execute. A warning message is usually informational and does not prevent the creation of a proper executable file. However, all warnings should eventually be corrected.

Note that the behaviour of the linker does not change when a message is disabled. For example, if a message that normally terminates the linker is disabled, the linker will still terminate but the message describing the reason for the termination will not be displayed. For this reason, you should only disable messages that are warnings.

The linker will ignore the severity of the message number. For example, some messages can be displayed as errors or warnings. It is not possible to disable the message when it is issued as a warning and display the message when it is issued as an error. In general, do not specify the severity of the message when specifying a message number.

The format of the "DISABLE" directive (short form "DISA") is as follows.

<i>DISABLE msg_num{, msg_num}</i>

DISABLE

where *description:*

msg_num is a message number. See the chapter entitled "Watcom Linker Diagnostic Messages" on page 213 for a list of messages and their corresponding numbers.

The following "DISABLE" directive will disable message 28 (an undefined symbol has been referenced).

```
disable 28
```

3.16 The DOSSEG Option

Formats: All

The "DOSSEG" option tells the Watcom Linker to order segments in a special way. The format of the "DOSSEG" option (short form "D") is as follows.

<i>OPTION DOSSEG</i>

When the "DOSSEG" option is specified, segments will be ordered in the following way.

1. all segments not belonging to group "DGROUP" with class "CODE"
2. all other segments not belonging to group "DGROUP"
3. all segments belonging to group "DGROUP" with class "BEGDATA"
4. all segments belonging to group "DGROUP" not with class "BEGDATA", "BSS" or "STACK"
5. all segments belonging to group "DGROUP" with class "BSS"
6. all segments belonging to group "DGROUP" with class "STACK"

A special segment belonging to class "BEGDATA" is defined when linking with Watcom run-time libraries. This segment is initialized with the hexadecimal byte pattern "01" and is the first segment in group "DGROUP" so that storing data at location 0 can be detected.

Segments belonging to class "BSS" contain uninitialized data. Note that this only includes uninitialized data in segments belonging to group "DGROUP". Segments belonging to class "STACK" are used to define the size of the stack used for your application. Segments belonging to the classes "BSS" and "STACK" are last in the segment ordering so that uninitialized data need not take space in the executable file.

When using Watcom run-time libraries, it is not necessary to specify the "DOSSEG" option. One of the object files in the Watcom run-time libraries contains a special record that specifies the "DOSSEG" option.

If no "DOSSEG" option is specified, segments are ordered in the order they are encountered by the Watcom Linker.

When the "DOSSEG" option is specified, the Watcom Linker defines two special variables. `_edata` defines the start of the "BSS" class of segments and `_end` defines the end of the "BSS" class of segments. Your program must not redefine these symbols.

3.17 The *ELIMINATE* Option

Formats: All

The "ELIMINATE" option can be used to enable dead code elimination. Dead code elimination is a process the linker uses to remove unreferenced segments from the application. The linker will only remove segments that contain code; unreferenced data segments will not be removed.

The format of the "ELIMINATE" option (short form "EL") is as follows.

<i>OPTION ELIMINATE</i>

Linking C/C++ Applications

Typically, a module of C/C++ code contains a number of functions. When this module is compiled, all functions will be placed in the same code segment. The chances of each function in the module being unreferenced are remote and the usefulness of the "ELIMINATE" option is greatly reduced.

In order to maximize the effect of the "ELIMINATE" option, the "zm" compiler option is available to tell the Watcom C/C++ compiler to place each function in its own code segment. This allows the linker to remove unreferenced functions from modules that contain many functions.

Note, that if a function is referenced by data, as in a jump table, the linker will not be able to eliminate the code for the function even if the data that references it is unreferenced.

Linking FORTRAN 77 Applications

The Watcom FORTRAN 77 compiler always places each function and subroutine in its own code segment, even if they are contained in the same module. Therefore when linking with the "ELIMINATE" option the linker will be able to eliminate code on a function/subroutine basis.

3.18 The ENDLINK Directive

Formats: All

The "ENDLINK" directive is used to indicate the end of a new set of linker commands that are to be processed after the current set of commands has been processed. The format of the "ENDLINK" directive (short form "ENDL") is as follows.

<i>ENDLINK</i>

The "STARTLINK" directive, described in "The STARTLINK Directive" on page 146, is used to indicate the start of the set of commands.

3.19 The EXIT Option

Formats: NetWare

The format of the "EXIT" option (short form "EX") is as follows.

```
OPTION EXIT=symbol_name
```

where *description:*

symbol_name specifies the name of the procedure that is executed when an NLM is unloaded.

The default name of the exit procedure is "_Stop".

Note that the exit procedure cannot prevent the NLM from being unloaded. Once the exit procedure has executed, the NLM will be unloaded. The "CHECK" option can be used to specify a check procedure that can prevent an NLM from being unloaded.

3.20 The EXPORT Directive

Formats: ELF, NetWare, OS/2, Win16, Win32

The "EXPORT" directive is used to tell the Watcom Linker which symbols are available for import by other executables.

3.20.1 EXPORT - OS/2, Win16, Win32 only

The "EXPORT" directive can be used to define the names and attributes of functions in Dynamic Link Libraries that are to be exported. An "EXPORT" definition must be specified for every Dynamic Link Library function that is to be made available externally.

Win16: An "EXPORT" directive is also required for the "window function". This function must be defined by all programs and is called by Windows to provide information to the program. For example, the window function is called when a window is created, destroyed or resized, when an item is selected from a menu, or when a scroll bar is being clicked with a mouse.

The format of the "EXPORT" directive (short form "EXP") is as follows.

```
EXPORT export{export}
```

or

```
EXPORT =lbc_file
```

OS/2 only:

```
export ::= entry_name[ordinal][=internal_name]  
[PRIVATE] [RESIDENT] [iopl_bytes]
```

Win16, Win32 only:

```
export ::= entry_name[ordinal][=internal_name]  
[PRIVATE] [RESIDENT]
```

where *description:*

entry_name is the name to be used by other applications to call the function.

ordinal is an ordinal value for the function. If the ordinal number is specified, other applications can reference the function by using this ordinal number.

internal_name is the actual name of the function and should only be specified if it differs from the entry name.

PRIVATE (no short form) specifies that the function's entry name should be included in the DLL's export table, but not included in any import library that the linker generates.

RESIDENT (short form "RES") specifies that the function's entry name should be kept resident in memory (i.e., added to the resident names table).

By default, the entry name is always made memory resident if an ordinal is not specified (i.e., it is implicitly RESIDENT). For 16-bit Windows, the limit on the size of the resident names table is 64K bytes. Memory resident entry names allow the operating system to resolve calls more efficiently when the call is by entry name rather than by ordinal.

If an ordinal is specified and RESIDENT is not specified, the entry name is added to the non-resident names table (i.e., it is implicitly non-RESIDENT). If both the ordinal and the RESIDENT keyword are specified, the symbol is placed in the resident names table.

If you do not want an entry name to appear in either the resident or non-resident names table, you can use the "ANONYMOUSEXPORT" directive described in "The ANONYMOUSEXPORT Directive" on page 24.

iopl_bytes (OS/2 only) is required for functions that execute with I/O privilege. *iopl_bytes* specifies that total size of the function's arguments in bytes. When such a function is executed, the specified number of bytes is copied from the caller's stack to the I/O-privileged function's stack. The maximum number of bytes allowed is 63.

lbc_file is a file specification for the name of a librarian command file. If no file extension is specified, a file extension of "lbc" is assumed. The linker will process the librarian command file and look for commands to the librarian that are used to create import library entries. These commands have the following form.

```
++sym.dll_name[.[altsym].export_name][.ordinal]
```

<i>where</i>	<i>description:</i>
<i>sym</i>	is the name of a symbol in a Dynamic Link Library.
<i>dll_name</i>	is the name of the Dynamic Link Library that defines <i>sym</i> .
<i>altsym</i>	is the name of a symbol in a Dynamic Link Library. When omitted, the default symbol name is <i>sym</i> .
<i>export_name</i>	is the name that an application that is linking to the Dynamic Link Library uses to reference <i>sym</i> . When omitted, the default export name is <i>sym</i> .
<i>ordinal</i>	is the ordinal value that can be used to identify <i>sym</i> instead of using the name <i>export_name</i> .

All other librarian commands will be ignored.

Notes:

1. By default, the Watcom C and C++ compilers append an underscore ('_') to all function names. This should be considered when specifying *entry_name* and *internal_name* in an "EXPORT" directive.
2. If the name contains characters that are special to the linker then the name may be placed inside apostrophes (e.g., `export 'myfunc@8'`).
3. If the `__export` declspec modifier is used in the source code, it is the equivalent of using the following linker directive:

```
EXPORT entry_name RESIDENT
```

3.20.2 EXPORT - ELF only

The "EXPORT" directive is used to tell the Watcom Linker which symbols are available for import by other executables. The format of the "EXPORT" directive (short form "EXP") is as follows.

EXPORT entry_name{,entry_name}

where description:

entry_name is the name of the exported symbol.

Notes:

1. By default, the Watcom C and C++ compilers append an underscore ('_') to all function names. This should be considered when specifying *entry_name* in an "EXPORT" directive.
2. If the name contains characters that are special to the linker then the name may be placed inside apostrophes (e.g., `export 'myfunc@8'`).

3.20.3 EXPORT - Netware only

The "EXPORT" directive is used to tell the Watcom Linker which symbols are available for import by other NLMs. The format of the "EXPORT" directive (short form "EXP") is as follows.

EXPORT entry_name{,entry_name}

where description:

entry_name is the name of the exported symbol.

Notes:

1. If the name contains characters that are special to the linker then the name may be placed inside apostrophes (e.g., `export 'myfunc@8'`).

3.21 The FILE Directive

Formats: All

The "FILE" directive is used to specify the object files and library modules that the Watcom Linker is to process. The format of the "FILE" directive (short form "F") is as follows.

```
FILE obj_spec{obj_spec}  
  
obj_spec ::= obj_file[(obj_module)]  
              /library_file[(obj_module)]
```

where *description:*

obj_file is a file specification for the name of an object file. If no file extension is specified, a file extension of "obj" is assumed if you are running a DOS, OS/2 or Windows-hosted version of the Watcom Linker. Also, if you are running a DOS, OS/2 or Windows-hosted version of the Watcom Linker, the object file specification can contain wild cards (*, ?). A file extension of "o" is assumed if you are running a QNX-hosted version of the Watcom Linker.

library_file is a file specification for the name of a library file. Note that the file extension of the library file (usually "lib") must be specified; otherwise an object file will be assumed. When a library file is specified, all object files in the library are included (whether required or not).

obj_module is the name of an object module defined in an object or library file.

Consider the following example.

Example:

```
wlink system my_os f \math\sin, mycos
```

The Watcom Linker is instructed to process the following object files:

```
\math\sin.obj  
mycos.obj
```

The object file "mycos.obj" is located in the current directory since no path was specified.

More than one "FILE" directive may be used. The following example is equivalent to the preceding one.

Example:

```
wlink system my_os f \math\sin f mycos
```

Thus, other directives may be placed between lists of object files.

The "FILE" directive can also specify object modules from a library file or object file. Consider the following example.

Example:

```
wlink system my_os f \math\math.lib(sin)
```

The Watcom Linker is instructed to process the object module "sin" contained in the library file "math.lib" in the directory "\math".

In the following example, the Watcom Linker will process the object module "sin" contained in the object file "math.obj" in the directory "\math".

Example:

```
wlink system my_os f \math\math(sin)
```

In the following example, the Watcom Linker will include all object modules contained in the library file "math.lib" in the directory "\math".

Example:

```
wlink system my_os f \math\math.lib
```

3.22 The *FORMAT* Directive

Formats: All

The "FORMAT" directive is used to specify the format of the executable file that the Watcom Linker is to generate. The format of the "FORMAT" directive (short form "FORM") is as follows.

FORMAT form

```

form ::= DOS [COM]
          / WINDOWS [win_dll] [MEMORY] [FONT]
          / WINDOWS NT [TNT] [dll_attrs]
          / OS2 [os2_type] [dll_attrs / os2_attrs]
          / PHARLAP [EXTENDED / REX / SEGMENTED]
          / NOVELL [NLM / LAN / DSK / NAM] 'description'
          / QNX [FLAT]
          / ELF [DLL]

win_dll ::= DLL [INITGLOBAL / INITINSTANCE]

dll_attrs ::= DLL [INITGLOBAL / INITINSTANCE]
              [TERMINSTANCE / TERMGLOBAL]

os2_type ::= FLAT / LE / LX

os2_attrs ::= PM / PMCOMPATIBLE / FULLSCREEN
              / PHYSDEVICE / VIRTDEVICE
    
```

where *description:*

DOS (short form "D") tells the Watcom Linker to generate a DOS "EXE" file.

The name of the executable file will have extension "exe". If "COM" is specified, a DOS "COM" file will be generated in which case the name of the executable file will have extension "com". Note that these default extensions can be overridden by using the "NAME" directive to name the executable file.

Not all programs can be generated in the "COM" format. The following rules must be followed.

1. The program must consist of only one physical segment. This implies that the size of the program (code and data) must be less than 64k.
2. The program must not contain any segment relocation. A warning message will be issued by the Watcom Linker each time a segment relocation is encountered.

A DOS "COM" file cannot contain debugging information. If you wish to debug a DOS "COM" file, you must use the "SYMFILE" option to instruct the Watcom Linker to place the debugging information in a separate file.

For more information on DOS executable file formats, see the chapter entitled "The DOS Executable File Format" on page 165.

WINDOWS tells the Watcom Linker to generate a Win16 (16-bit Windows) executable file.

The name of the executable file will have extension "exe". If "DLL" (short form "DL") is specified, a Dynamic Link Library will be generated; the name of the executable file will also have extension "exe". Note that these default extensions can be overridden by using the "NAME" directive to name the executable file.

Specifying "INITGLOBAL" (short form "INITG") will cause Windows to call an initialization routine the first time the Dynamic Link Library is loaded. The "INITGLOBAL" option should be used with "OPTION ONEAUTODATA" (the default for Dynamic Link Libraries). If the "INITGLOBAL" option is used with "OPTION MANYAUTODATA", the initialization code will be called once for the first data segment allocated but not for subsequent allocations (this is generally not desirable behaviour and will likely cause a program fault).

Specifying "INITINSTANCE" (short form "INITI") will cause Windows to call an initialization routine each time the Dynamic Link Library is used by a process. The "INITINSTANCE" option should be used with "OPTION MANYAUTODATA" (the default for executable programs).

In either case, the initialization routine is defined by the start address. If neither "INITGLOBAL" or "INITINSTANCE" is specified, "INITGLOBAL" is assumed.

Specifying "MEMORY" (short form "MEM") indicates that the application will run in standard or enhanced mode. If Windows 3.0 is running in standard and enhanced mode, and "MEMORY" is not specified, a warning message will be issued. The "MEMORY" specification was used in the transition from Windows 2.0 to Windows 3.0. The "MEMORY" specification is ignored in Windows 3.1 or later.

Specifying "FONT" (short form "FO") indicates that the proportional-spaced system font can be used. Otherwise, the old-style mono-spaced system font will be used. The "FONT" specification was used in the transition from Windows 2.0 to Windows 3.0. The "FONT" specification is ignored in Windows 3.1 or later.

For more information on Windows executable file formats, see the chapter entitled "The Win16 Executable and DLL File Formats" on page 199.

WINDOWS NT tells the Watcom Linker to generate a Win32 executable file ("PE" format).

If "TNT" is specified, an executable for the Phar Lap TNT DOS extender is created. A "PL" format (rather than "PE") executable is created so that the Phar Lap TNT DOS extender will always run the application (including under Windows NT).

If "DLL" (short form "DL") is specified, a Dynamic Link Library will be generated in which case the name of the executable file will have extension "dll". Note that these default extensions can be overridden by using the "NAME" directive to name the executable file.

Specifying "INITGLOBAL" (short form "INITG") will cause the initialization routine to be called the first time the Dynamic Link Library is loaded.

Specifying "INITINSTANCE" (short form "INITI") will cause the initialization routine to be called each time the Dynamic Link Library is referenced by a process.

In either case, the initialization routine is defined by the start address. If neither "INITGLOBAL" or "INITINSTANCE" is specified, "INITGLOBAL" is assumed.

It is also possible to specify whether the initialization routine is to be called at DLL termination or not. Specifying "TERMGLOBAL" (short form "TERMG") will cause the initialization routine to be called when the last instance of the Dynamic Link Library is terminated. Specifying "TERMINSTANCE" (short form "TERMI") will cause the initialization routine to be called each time an instance of the Dynamic Link Library is terminated. Note that the initialization routine is passed an argument indicating whether it is being called during DLL initialization or DLL termination. If "INITINSTANCE" is used and no termination option is specified, "TERMINSTANCE" is assumed. If "INITGLOBAL" is used and no termination option is specified, "TERMGLOBAL" is assumed.

For more information on Windows NT executable file formats, see the chapter entitled "The Win32 Executable and DLL File Formats" on page 207.

OS2 tells the Watcom Linker to generate an OS/2 executable file format.

The name of the executable file will have extension "exe". If "LE" is specified, an early form of the OS/2 32-bit linear executable will be generated. This executable file format is required by Tenberry Software's DOS/4G and DOS/4GW DOS extenders.

In order to improve load time and minimize the size of the executable file, the OS/2 32-bit linear executable file format was changed. If "LX" or "FLAT" (short form "FL") is specified, the new form of the OS/2 32-bit linear executable will be generated. This executable file format is required by the FlashTek DOS extender and 32-bit OS/2 executables.

If "FLAT", "LX" or "LE" is not specified, an OS/2 16-bit executable will be generated.

If "DLL" (short form "DL") is specified, a Dynamic Link Library will be generated in which case the name of the executable file will have extension "dll". Note that these default extensions can be overridden by using the "NAME" directive to name the executable file.

Specifying "INITGLOBAL" (short form "INITG") will cause the initialization routine to be called the first time the Dynamic Link Library is loaded. The "INITGLOBAL" option should be used with "OPTION ONEAUTODATA" (the default for Dynamic Link Libraries). If the "INITGLOBAL" option is used with "OPTION MANYAUTODATA", the initialization code will be called once for the first data segment allocated but not for subsequent allocations (this is generally not desirable behaviour and will likely cause a program fault).

Specifying "INITINSTANCE" (short form "INITI") will cause the initialization routine to be called each time the Dynamic Link Library is referenced by a process. The "INITINSTANCE" option should be used with "OPTION MANYAUTODATA" (the default for executable programs).

In either case, the initialization routine is defined by the start address. If neither "INITGLOBAL" or "INITINSTANCE" is specified, "INITGLOBAL" is assumed.

For OS/2 32-bit linear executable files, it is also possible to specify whether the initialization routine is to be called at DLL termination or not. Specifying "TERMGLOBAL" (short form "TERMG") will cause the initialization routine

to be called when the last instance of the Dynamic Link Library is terminated. Specifying "TERMINSTANCE" (short form "TERMI") will cause the initialization routine to be called each time an instance of the Dynamic Link Library is terminated. Note that the initialization routine is passed an argument indicating whether it is being called during DLL initialization or DLL termination. If "INITINSTANCE" is used and no termination option is specified, "TERMINSTANCE" is assumed. If "INITGLOBAL" is used and no termination option is specified, "TERMGLOBAL" is assumed.

If "PM" is specified, a Presentation Manager application will be created. The application uses the API provided by the Presentation Manager and must be executed in the Presentation Manager environment.

If "PMCOMPATIBLE" (short form "PMC") is specified, an application compatible with Presentation Manager will be created. The application can run inside the Presentation Manager or it can run in a separate screen group. An application can be of this type if it uses the proper subset of OS/2 video, keyboard, and mouse functions supported in the Presentation Manager applications. This is the default.

If "FULLSCREEN" (short form "FULL") is specified, an OS/2 full screen application will be created. The application will run in a separate screen group from the Presentation Manager.

If "PHYSDEVICE" (short form "PHYS") is specified, the executable file is marked as a physical device driver.

If "VIRTDEVICE" (short form "VIRT") is specified, the executable file is marked as a virtual device driver.

For more information on OS/2 executable file formats, see the chapter entitled "The OS/2 Executable and DLL File Formats" on page 181.

PHARLAP (short form "PHAR") tells the Watcom Linker to generate an executable file that will run under Phar Lap's 386DOS-Extender.

There are 4 forms of executable files: simple, extended, relocatable and segmented. If "EXTENDED" (short form "EXT") is specified, an extended form of the executable file with file extension "exp" will be generated. If "REX" is specified, a relocatable executable file with file extension "rex" will be generated. If "SEGMENTED" (short form "SEG") is specified, a segmented executable file with file extension "exp" will be generated. If neither "EXTENDED", "REX" or "SEGMENTED" is specified, a simple executable file

with file extension "exp" will be generated. Note that the default file extensions can be overridden by using the "NAME" directive to name the executable file.

The simple form is for flat model 386 applications. It is the only format that can be loaded by earlier versions of 386|DOS-Extender (earlier than 1.2).

The extended form is used for flat model applications that have been linked in a way which requires a method of specifying more information for 386|DOS-Extender than possible with the simple form.

The relocatable form is similar to the simple form. Unique to the relocatable form is an offset relocation table. This allows the loader to load the program at any location it chooses.

The segmented form is used for embedded system applications like Intel RMX. These executables cannot be loaded by 386|DOS-Extender.

A simple form of the executable file is generated in all but the following cases.

1. "EXTENDED" is specified in the "FORMAT" directive.
2. The "RUNTIME" directive is specified. Options specified by the "RUNTIME" directive can only be specified in the extended form of the executable file.
3. The "OFFSET" option is specified. The value specified in the "OFFSET" option can only be specified in the extended form of the executable file.
4. "REX" is specified in the "FORMAT" directive. In this case, the relocatable form will be generated. You must not specify the "RUNTIME" directive or the "OFFSET" option when generating the relocatable form.
5. "SEGMENTED" is specified in the "FORMAT" directive. In this case, the segmented form will be generated.

For more information on Phar Lap executable file formats, see the chapter entitled "The Phar Lap Executable File Format" on page 189.

NOVELL (short form "NOV") tells the Watcom Linker to generate a NetWare 386 executable file, more commonly called a NetWare Loadable Module (NLM).

NLMs are further classified according to their function. The executable file will have a file extension that depends on the class of the NLM being generated. The following describes the classification of NLMs.

LAN instructs the Watcom Linker to generate a LAN driver. A LAN driver is a device driver for Local Area Network hardware. A file extension of "lan" is used for the name of the executable file.

DSK instructs the Watcom Linker to generate a disk driver. A file extension of "dsk" is used for the name of the executable file.

NAM instructs the Watcom Linker to generate a file system name-space support module. A file extension of "nam" is used for the name of the executable file.

NLM instructs the Watcom Linker to generate a utility or server application. This is the default. A file extension of "nlm" is used for the name of the executable file.

description is a textual description of the program being linked.

For more information on NetWare 386 executable file formats, see the chapter entitled "The NetWare 386 Executable File Format" on page 175.

QNX tells the Watcom Linker to generate a QNX executable file.

If "FLAT" (short form "FL") is specified, a 32-bit flat executable file is generated.

Under QNX, no file extension is added to the executable file name.

Under other operating systems, the name of the executable file will have the extension "qnx". Note that this default extension can be overridden by using the "NAME" directive to name the executable file.

For more information on QNX executable file formats, see the chapter entitled "The QNX Executable File Format" on page 195.

ELF tells the Watcom Linker to generate an ELF format executable file.

ELF format DLLs can also be created.

For more information on ELF executable file formats, see the chapter entitled "The ELF Executable File Format" on page 171.

If no "FORMAT" directive is specified, the executable file format will be selected for each of the following host systems in the way described.

DOS If 16-bit object files are encountered, a 16-bit DOS executable will be created.
If 32-bit object files are encountered, a 32-bit DOS/4G executable will be created.

OS/2 If 16-bit object files are encountered, a 16-bit OS/2 executable will be created.
If 32-bit object files are encountered, a 32-bit OS/2 executable will be created.

QNX If 16-bit object files are encountered, a 16-bit QNX executable will be created.
If 32-bit object files are encountered, a 32-bit QNX executable will be created.

Windows NT If 16-bit object files are encountered, a 16-bit Windows executable will be created. If 32-bit object files are encountered, a 32-bit Win32 executable will be created.

Windows 95 If 16-bit object files are encountered, a 16-bit Windows executable will be created. If 32-bit object files are encountered, a 32-bit Win32 executable will be created.

3.23 The HEAPSIZE Option

Formats: OS/2, QNX, Win16, Win32

The "HEAPSIZE" option specifies the size of the heap required by the application. The format of the "HEAPSIZE" option (short form "H") is as follows.

<i>OPTION HEAPSIZE=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

[0x] d { d } [k | m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n specifies the size of the heap. The default heap size is 0 bytes. The maximum value of *n* is 65536 (64K) for 16-bit applications and 4G for 32-bit applications which is the maximum size of a physical segment. Actually, for a particular application, the maximum value of *n* is 64K or 4G less the size of group "DGROUP".

3.24 The HELP Option

Formats: NetWare

The "HELP" option specifies the file name of an internationalized help file whose language corresponds to the message file bound to this NLM.

The format of the "HELP" option (short form "HE") is as follows.

<i>OPTION HELP=help_file</i>

where *description:*

help_file is the name of the help file.

3.25 The IMPFILE Option

Formats: NetWare, OS/2, Win16, Win32

The "IMPFILE" option requests the linker to produce a Watcom Library Manager command file that can be used to create an import library that corresponds to the DLL that is being generated. This option is useful in situations where the Watcom Linker cannot create an import library file when you have specified the "IMPLIB" option (i.e., the linker fails to launch Watcom Library Manager).

The format of the "IMPFILE" option (short form "IMPF") is as follows.

<i>OPTION IMPFILE[=<i>imp_file</i>]</i>
--

where *description:*

imp_file is a file specification for the name of the command file that can be used to create the import library file using the Watcom Library Manager. If no file extension is specified, no file extension is assumed.

By default, no command file is generated. Specifying this option causes the linker to generate an import library command file. The import library command file contains a list of the entry points in your DLL. When this command file is processed by the Watcom Library Manager, an import library file will be produced.

If no file name is specified, the import library command file will have a default file extension of "lbc" and the same file name as the DLL file. Note that the import library command file will be created in the same directory as the DLL file. The DLL file path and name can be specified in the "NAME" directive.

Alternatively, a library command file path and name can be specified. The following directive instructs the linker to generate a import library command file and call it "mylib.lcf" regardless of the name of the executable file.

```
option impfile=mylib.lcf
```

You can also specify a path and/or file extension when using the "IMPFILE=" form of the "IMPFILE" option.

3.26 The IMPLIB Option

Formats: NetWare, OS/2, Win16, Win32

The "IMPLIB" option requests the linker to produce an import library that corresponds to the DLL that is being generated. The format of the "IMPLIB" option (short form "IMPL") is as follows.

*OPTION IMPLIB[=*imp_lib*]*

where *description:*

imp_lib is a file specification for the name of the import library file. If no file extension is specified, a file extension of "lib" is assumed.

By default, no library file is generated. Specifying this option causes the Watcom Linker to generate an import library file. The import library file contains a list of the entry points in your DLL.

If no file name is specified, the import library file will have a default file extension of "lib" and the same file name as the DLL file. Note that the import library file will be created in the same directory as the DLL file. The DLL file path and name can be specified in the "NAME" directive.

Alternatively, a library file path and name can be specified. The following directive instructs the linker to generate a library file and call it "mylib.imp" regardless of the name of the executable file.

```
option implib=mylib.imp
```

You can also specify a path and/or file extension when using the "IMPLIB=" form of the "IMPLIB" option.

Note: At present, the linker spawns the Watcom Library Manager to create the import library file.

3.27 The *IMPORT* Directive

Formats: ELF, NetWare, OS/2, Win16, Win32

The "IMPORT" directive is used to tell the Watcom Linker what symbols are defined externally in other executables.

3.27.1 *IMPORT - OS/2, Win16, Win32 only*

The "IMPORT" directive describes a function that belongs to a Dynamic Link Library. The format of the "IMPORT" directive (short form "IMP") is as follows.

```
IMPORT import{,import}
```

```
import ::= internal_name module_name[.entry_name | ordinal]
```

where *description:*

internal_name is the name the application used to call the function.

module_name is the name of the Dynamic Link Library. Note that this need not be the same as the file name of the executable file containing the Dynamic Link Library. This name corresponds to the name specified by the "MODNAME" option when the Dynamic Link Library was created.

entry_name is the actual name of the function as defined in the Dynamic Link Library.

ordinal is the ordinal value of the function. The ordinal number is an alternate method that can be used to reference a function in a Dynamic Link Library.

Notes:

1. By default, the Watcom C and C++ compilers append an underscore ('_') to all function names. This should be considered when specifying *internal_name* and *entry_name* in an "IMPORT" directive.
2. If the name contains characters that are special to the linker then the name may be placed inside apostrophes (e.g., `import 'myfunc@8'`).

The preferred method to resolve references to Dynamic Link Libraries is through the use of import libraries. See the sections entitled "Using a Dynamic Link Library" on page 185, "Using a Dynamic Link Library" on page 204, or "Using a Dynamic Link Library" on page 211 for more information on import libraries.

3.27.2 IMPORT - ELF only

The "IMPORT" directive is used to tell the Watcom Linker what symbols are defined externally in other executables. The format of the "IMPORT" directive (short form "IMP") is as follows.

IMPORT external_name{,external_name}

where *description:*

external_name is the name of the external symbol.

Notes:

1. By default, the Watcom C and C++ compilers append an underscore ('_') to all function names. This should be considered when specifying *external_name* in an "IMPORT" directive.
2. If the name contains characters that are special to the linker then the name may be placed inside apostrophes (e.g., `import 'myfunc@8'`).

3.27.3 IMPORT - Netware only

The "IMPORT" directive is used to tell the Watcom Linker what symbols are defined externally in other NLMs. The format of the "IMPORT" directive (short form "IMP") is as follows.

IMPORT external_name{,external_name}

where *description:*

external_name is the name of the external symbol.

Notes:

1. If the name contains characters that are special to the linker then the name may be placed inside apostrophes (e.g., `import 'myfunc@8'`).

If an NLM contains external symbols, the NLMs that define the external symbols must be loaded before the NLM that references the external symbols is loaded.

3.28 The @ Directive

The "@" directive instructs the Watcom Linker to process directives from an alternate source. The format of the "@" directive is as follows.

<p><i>@directive_var</i> or <i>@directive_file</i></p>
--

where *description:*

directive_var is the name of an environment variable. The directives specified by the value of *directive_var* will be processed.

directive_file is a file specification for the name of a linker directive file. A file extension of ".lnk" is assumed if no file extension is specified.

The environment variable approach to specifying linker directives allows you to specify commonly used directives without having to specify them each time you invoke the Watcom Linker. If the environment variable "wlink" is set as in the following example,

```
set wlink=debug watcom all option map, verbose library math  
wlink @wlink
```

then each time the Watcom Linker is invoked, full debugging information will be generated, a verbose map file will be created, and the library file "math.lib" will be searched for undefined references.

A linker directive file is useful, for example, when the linker input consists of a large number of object files and you do not want to type their names on the command line each time you link your program. Note that a linker directive file can also include other linker directive files.

Let the file "memos.lnk" be a directive file containing the following lines.

```
system my_os
name memos
file memos
file actions
file read
file msg
file prompt
file memmgr
library \termio\screen
library \termio\keyboard
```

Win16 only: We must also use the "EXPORT" directive to define the window function. This is done using the following directive.

```
export window_function
```

Consider the following example.

Example:

```
wlink @memos
```

The Watcom Linker is instructed to process the contents of the directive file "memos.lnk". The executable image file will be called "memos.exe". The following object files will be loaded from the current directory.

```
memos.obj
actions.obj
read.obj
msg.obj
prompt.obj
memmgr.obj
```

If any unresolved symbol references remain after all object files have been processed, the library files "screen.lib" and "keyboard.lib" in the directory "\termio" will be searched (in the order listed).

Notes:

1. In the above example, we did not provide the file extension when the directive file was specified. The Watcom Linker assumes a file extension of ".lnk" if none is present.
2. It is not necessary to list each object file and library with a separate directive. The following linker directive file is equivalent.

```
system my_os
name memos
file memos,actions,read,msg,prompt,memmgr
library \termio\screen,\termio\keyboard
```

However, if you want to selectively specify what debugging information should be included, the first style of directive file will be easier to use. This is illustrated in the following sample directive file.

```
system my_os
name memos
debug watcom lines
file memos
debug watcom all
file actions
debug watcom lines
file read
file msg
file prompt
file memmgr
debug watcom
library \termio\screen
library \termio\keyboard
```

3. Information for a particular directive can span directive files. This is illustrated in the following sample directive file.

```
system my_os
file memos,actions,read,msg,prompt,memmgr
file @dbgfiles
library \termio\screen
library \termio\keyboard
```

The directive file "dbgfiles.lnk" contains, for example, those object files that are used for debugging purposes.

3.29 The INCREMENTAL Option

Formats: ELF, OS/2, PharLap, QNX, Win16, Win32

The "INCREMENTAL" option can be used to enable incremental linking. Incremental linking is a process whereby the linker attempts to modify the existing executable file by changing only those portions for which new object files are provided.

The format of the "INCREMENTAL" option (short form "INC") is as follows.

<i>OPTION INCREMENTAL[=<i>inc_file_name</i>]</i>
--

where *description:*

inc_file_name is a file specification for the name of the incremental information file. If no file extension is specified, a file extension of "ilk" is assumed.

This option engages the incremental linking feature of the linker. This option must be one of the first options encountered in the list of directives and options supplied to the linker. If the option is presented too late, the linker will issue a diagnostic message.

By default, the incremental information file has the same name as the program except with an "ilk" extension unless the "NAME" directive has not been seen yet. If this is the case then the file is called `__WLINK.ILK`.

The linker's incremental linking technique is very resistant to changes in the underlying object files - there are very few cases where an incremental re-link is not possible. The options "ELIMINATE" and "VFREMOVAL" cannot be used at the same time as incremental linking.

It is possible, over time, to accumulate unneeded functions in the executable by using incremental linking. To guarantee an executable of minimum size, you can cause a full relink by deleting the ".ilk" file or by not specifying the "INCREMENTAL" option.

Do not use a post processor like the Watcom Resource Compiler on the executable file since this will damage the data structures maintained by the linker. Add resources to the executable file using the "RESOURCE" option which is described in "The RESOURCE Option" on page 130.

Note: Only Dwarf debugging information is supported with incremental linking.

3.30 The *INTERNALRELOCS* Option

Formats: OS/2

The "INTERNALRELOCS" option is used with LX format executables under 32-bit OS/2. By default, OS/2 executables do not contain internal relocation information and OS/2 Dynamic Link Libraries do contain internal relocation information. This option causes the Watcom Linker to include internal relocation information in OS/2 LX format executables.

The format of the "INTERNALRELOCS" option (short form "INT") is as follows.

<i>OPTION INTERNALRELOCS</i>

3.31 The LANGUAGE Directive

Formats: All

The "LANGUAGE" directive is used to specify the language in which strings in the Watcom Linker directives are specified. The format of the "LANGUAGE" directive (short form "LANG") is as follows.

```
LANGUAGE lang
```

```
lang ::= JAPANESE / CHINESE / KOREAN
```

JAPANESE (short form "JA") specifies that strings are to be handled as if they contained characters from the Japanese Double-Byte Character Set (DBCS).

CHINESE (short form "CH") specifies that strings are to be handled as if they contained characters from the Chinese Double-Byte Character Set (DBCS).

KOREAN (short form "KO") specifies that strings are to be handled as if they contained characters from the Korean Double-Byte Character Set (DBCS).

3.32 The LIBFILE Directive

Formats: All

The "LIBFILE" directive is used to specify the object files that the Watcom Linker is to process. The format of the "LIBFILE" directive (short form "LIBF") is as follows.

```
LIBFILE obj_spec{,obj_spec}  
  
obj_spec ::= obj_file / library_file
```

where *description:*

obj_file is a file specification for the name of an object file. If no file extension is specified, a file extension of "obj" is assumed if you are running a DOS, OS/2 or Windows-hosted version of the Watcom Linker. Also, if you are running a DOS, OS/2 or Windows-hosted version of the Watcom Linker, the object file specification can contain wild cards (*, ?). A file extension of "o" is assumed if you are running a QNX-hosted version of the Watcom Linker.

library_file is a file specification for the name of a library file. Note that the file extension of the library file (usually "lib") must be specified; otherwise an object file will be assumed. When a library file is specified, all object files in the library are included (whether required or not).

The difference between the "LIBFILE" directive and the "FILE" directive is as follows.

1. When searching for an object or library file specified in a "LIBFILE" directive, the default directory will be searched first, followed by the paths specified in the "LIBPATH" directive, and finally the paths specified in the "LIB" environment variable. Note that if the object or library file name contains a path, only the specified path will be searched.
2. Object or library file names specified in a "LIBFILE" directive will not be used to create the name of the executable file when no "NAME" directive is specified.

Essentially, object files that appear in "LIBFILE" directives are viewed as components of a library that have not been explicitly placed in a library file.

Consider the following linker directive file.

```
libpath \libs  
libfile mystart  
path \objs  
file file1, file2
```

The Watcom Linker is instructed to process the following object files:

```
\libs\mystart.obj  
\objs\file1.obj  
\objs\file2.obj
```

Note that the executable file will have file name "file1" and not "mystart".

3.33 The LIBPATH Directive

Formats: All

The "LIBPATH" directive is used to specify the directories that are to be searched for library files appearing in subsequent "LIBRARY" directives and object files appearing in subsequent "LIBFILE" directives. The format of the "LIBPATH" directive (short form "LIBP") is as follows.

***LIBPATH* [path_name{;path_name}]**

where *description:*

path_name is a path name.

Consider a directive file containing the following linker directives.

```
file test
libpath \math
library trig
libfile newsin
```

First, the Watcom Linker will process the object file "test.obj" from the default directory. The object file "newsin.obj" will then be processed, searching the default directory first. If "newsin.obj" is not in the default directory, the "\math" directory will be searched. If any unresolved references remain after processing the object files, the library file "trig.lib" will be searched. If the file "trig.lib" does not exist in the default directory, the "\math" directory will be searched.

It is also possible to specify a list of paths in a "LIBPATH" directive. Consider the following example.

```
libpath \newmath;\math
library trig
```

When processing undefined references, the Watcom Linker will attempt to process the library file "trig.lib" in the default directory. If "trig.lib" does not exist in the default directory, the "\newmath" directory will be searched. If "trig.lib" does not exist in the "\newmath" directory, the "\math" directory will be searched.

If the name of a library file appearing in a "LIBRARY" directive or the the name of an object file appearing in a "LIBFILE" directive contains a path specification, only the specified path will be searched.

Note that

```
libpath path1  
libpath path2
```

is equivalent to the following.

```
libpath path2;path1
```

3.34 The *LIBRARY* Directive

Formats: All

The "LIBRARY" directive is used to specify the library files to be searched when unresolved symbols remain after processing all specified input object files. The format of the "LIBRARY" directive (short form "L") is as follows.

LIBRARY *library_file*{*library_file*}

where *description:*

library_file is a file specification for the name of a library file. If no file extension is specified, a file extension of "lib" is assumed.

Consider the following example.

Example:

```
wlink system my_os file trig lib \math\trig, \cplx\trig
```

The Watcom Linker is instructed to process the following object file:

```
trig.obj
```

If any unresolved symbol references remain after all object files have been processed, the following library files will be searched:

```
\math\trig.lib  
\cplx\trig.lib
```

More than one "LIBRARY" directive may be used. The following example is equivalent to the preceding one.

Example:

```
wlink system my_os f trig lib \math\trig lib \cplx\trig
```

Thus other directives may be placed between lists of library files.

3.34.1 Searching for Libraries Specified in Environment Variables

The "LIB" environment variable can be used to specify a list of paths that will be searched for library files. The "LIB" environment variable can be set using the "set" command as follows:

```
set lib=\graphics\lib;\utility
```

Consider the following "LIBRARY" directive and the above definition of the "LIB" environment variable.

```
library \mylibs\util, graph
```

If undefined symbols remain after processing all object files specified in all "FILE" directives, the Watcom Linker will resolve these references by searching the following libraries in the specified order.

1. the library file "\mylibs\util.lib"
2. the library file "graph.lib" in the current directory
3. the library file "\graphics\lib\graph.lib"
4. the library file "\utility\graph.lib"

Notes:

1. If a library file specified in a "LIBRARY" directive contains an absolute path specification, the Watcom Linker will not search any of the paths specified in the "LIB" environment string for the library file. Under QNX, an absolute path specification is one that begins the "/" character. Under all other operating systems, an absolute path specification is one that begins with a drive specification or the "\" character.
2. Once a library file has been found, no further elements of the "LIB" environment variable are searched for other libraries of the same name. That is, if the library file "\graphics\lib\graph.lib" exists, the library file "\utility\graph.lib" will not be searched even though unresolved references may remain.

3.34.2 Converting Libraries Created using Phar Lap 386|LIB

Phar Lap's librarian, 386|LIB, creates libraries whose dictionary is a different format from the one used by other librarians. For this reason, linking an application using the Watcom Linker with libraries created using 386|LIB will not work. Library files created using 386|LIB must be converted to the form recognized by the Watcom Linker. This is achieved by issuing the following WLIB command.

```
wlib newlib +pharlib.lib
```

The library file "pharlib.lib" is a library created using 386|LIB. The library file "newlib.lib" will be created so that the Watcom Linker can now process it.

3.35 The *LINEARRELOCS* Option

Formats: QNX

The "LINEARRELOCS" option instructs the linker to generate offset fixups in addition to the normal segment fixups. The offset fixups allow the system to move pieces of code and data that were loaded at a particular offset within a segment to another offset within the same segment.

The format of the "LINEARRELOCS" option (short form "LI") is as follows.

<i>OPTION LINEARRELOCS</i>

3.36 The *LONGLIVED* Option

Formats: QNX

The "LONGLIVED" option specifies that the application being linked will reside in memory, or be active, for a long period of time (e.g., background tasks). The memory manager, knowing an application is "LONGLIVED", allocates memory for the application so as to reduce fragmentation.

The format of the "LONGLIVED" option (short form "LO") is as follows.

<i>OPTION LONGLIVED</i>

3.37 The MANGLEDNAMES Option

Formats: All

The "MANGLEDNAMES" option should only be used if you are developing a Watcom C++ application. Due to the nature of C++, the Watcom C++ compiler generates mangled names for symbols. A mangled name for a symbol includes the following.

1. symbol name
2. scoping information
3. typing information

This information is stored in a cryptic form with the symbol. When the linker encounters a mangled name in an object file, it formats the above information and produces this name in the map file.

If you would like the linker to produce the mangled name as it appeared in the object file, specify the "MANGLEDNAMES" option.

The format of the "MANGLEDNAMES" option (short form "MANG") is as follows.

<i>OPTION MANGLEDNAMES</i>

3.38 The MANYAUTODATA Option

Formats: OS/2, Win16

The "MANYAUTODATA" option specifies that a copy of the automatic data segment (default data segment defined by the group "DGROUP"), for the program module or Dynamic Link Library (DLL) being created, is made for each instance. The format of the "MANYAUTODATA" option (short form "MANY") is as follows.

<i>OPTION MANYAUTODATA</i>

The default for a program module is "MANYAUTODATA" and for a Dynamic Link Library is "ONEAUTODATA". If you do not want the data area of a DLL to be shared across multiple applications, then you should specify "OPTION MANYAUTODATA".

Win16: Note, however, that this attribute is not supported by Windows 3.x for 16-bit DLLs.

You should also see the related section entitled "The FORMAT Directive" on page 56 for information on the "INITINSTANCE", "TERMINSTANCE", "INITGLOBAL", and "TERMGLOBAL" DLL attributes.

3.39 The MAP Option

Formats: All

The "MAP" option controls the generation of a map file. The format of the "MAP" option (short form "M") is as follows.

*OPTION MAP[=*map_file*]*

where *description:*

map_file is a file specification for the name of the map file. If no file extension is specified, a file extension of "map" is assumed.

By default, no map file is generated. Specifying this option causes the Watcom Linker to generate a map file. The map file is simply a memory map of your program. That is, it specifies the relative location of all global symbols in your program. The map file also contains the size of your program.

If no file name is specified, the map file will have a default file extension of "map" and the same file name as the executable file. Note that the map file will be created in the current directory even if the executable file name specified in the "NAME" directive contains a path specification.

Alternatively, a file name can be specified. The following directive instructs the linker to generate a map file and call it "myprog.map" regardless of the name of the executable file.

```
option map=myprog
```

You can also specify a path and/or file extension when using the "MAP=" form of the "MAP" option.

3.40 The MAXDATA Option

Formats: PharLap

The format of the "MAXDATA" option (short form "MAXD") is as follows.

<i>OPTION MAXDATA=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

[0x] d { d } [k | m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n specifies the maximum number of bytes, in addition to the memory required by executable image, that may be allocated by 386]DOS-Extender at the end of the loaded executable image. No more than *n* bytes will be allocated.

If the "MAXDATA" option is not specified, a default value of hexadecimal ffffffff is assumed. This means that 386]DOS-Extender will allocate all available memory to the program at load time.

3.41 The MAXERRORS Option

Formats: All

The "MAXERRORS" option can be used to set a limit on the number of error messages generated by the linker. Note that this does not include warning messages. When this limit is reached, the linker will issue a fatal error and terminate.

The format of the "MAXERRORS" option (short form "MAXE") is as follows.

<i>OPTION MAXERRORS=n</i>

where *description:*

n is the maximum number of error messages issued by the linker.

3.42 The MESSAGES Option

Formats: NetWare

The "MESSAGES" option specifies the file name of an internationalized message file that contains the default messages for the NLM. This is the name of the default message file to load for NLMs that are enabled. Enabling allows the same NLM to display messages in different languages by switching message files.

The format of the "MESSAGES" option (short form "MES") is as follows.

<i>OPTION MESSAGES=msg_file</i>

where *description:*

msg_file is the name of the message file.

3.43 The MINDATA Option

Formats: PharLap

The format of the "MINDATA" option (short form "MIND") is as follows.

<i>OPTION MINDATA=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

$$[0x]d\{d\}[k|m]$$

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n specifies the minimum number of bytes, in addition to the memory required by executable image, that must be allocated by 386|DOS-Extender at the end of the loaded executable image. If *n* bytes are not available, the program will not be executed.

If the "MINDATA" option is not specified, a default value of zero is assumed. This means that 386|DOS-Extender will load the program as long as there is enough memory for the load image; no extra memory is required.

3.44 The MODNAME Option

Formats: OS/2, Win16, Win32

The "MODNAME" option specifies a name to be given to the module being created. The format of the "MODNAME" option (short form "MODN") is as follows.

<i>OPTION MODNAME=module_name</i>

where *description:*

module_name is the name of a Dynamic Link Library.

Once a module has been loaded (whether it be a program module or a Dynamic Link Library), *mod_name* is the name of the module known to the operating system. If the "MODNAME" option is not used to specify a module name, the default module name is the name of the executable file without the file extension.

3.45 The MODFILE Directive

Formats: All

The "MODFILE" directive instructs the linker that only the specified object files have changed. The format of the "MODFILE" directive (short form "MODF") is as follows.

MODFILE obj_file{,obj_file}

where *description:*

obj_file is a file specification for the name of an object file. If no file extension is specified, a file extension of ".obj" is assumed if you are running a DOS, OS/2 or Windows-hosted version of the Watcom Linker. Also, if you are running a DOS, OS/2 or Windows-hosted version of the Watcom Linker, the object file specification can contain wild cards (*, ?). A file extension of ".o" is assumed if you are running a QNX-hosted version of the Watcom Linker.

This directive is used only in concert with incremental linking. This directive tells the linker that only the specified object files have changed. When this option is specified, the linker will not check the dates on any of the object files or libraries when incrementally linking.

3.46 The MODTRACE Directive

Formats: All

The "MODTRACE" directive instructs the Watcom Linker to print a list of all modules that reference the symbols defined in the specified modules. The format of the "MODTRACE" directive (short form "MODT") is as follows.

<i>MODTRACE module_name{,module_name}</i>

where *description:*

module_name is the name of an object module defined in an object or library file.

The information is displayed in the map file. Consider the following example.

Example:

```
wlink system my_os op map file test lib math modt trig
```

If the module "trig" defines the symbols "sin" and "cos", the Watcom Linker will list, in the map file, all modules that reference the symbols "sin" and "cos".

3.47 The *MODULE* Directive

Formats: ELF, NetWare

The "MODULE" directive is used to specify the DLLs or NLMs to be loaded before this executable is loaded. The format of the "MODULE" directive (short form "MODU") is as follows.

MODULE *module_name*{*module_name*}

where *description:*

module_name is the file name of a DLL or NLM.

WARNING! Versions 3.0 and 3.1 of the NetWare 386 operating system do not support the automatic loading of modules specified in the "MODULE" directive. You must load them manually.

3.48 The *MULTILOAD* Option

Formats: NetWare

The "MULTILOAD" option specifies that the module can be loaded more than once by a "load" command. The format of the "MULTILOAD" option (short form "MULTIL") is as follows.

<i>OPTION MULTILOAD</i>

If the "MULTILOAD" option is not specified, it will not be possible to load the module more than once using the "load" command.

3.49 The NAME Directive

Formats: All

The "NAME" directive is used to provide a name for the executable file generated by the Watcom Linker. The format of the "NAME" directive (short form "N") is as follows.

<i>NAME exe_file</i>

where *description:*

exe_file is a file specification for the name of the executable file. Under QNX, no file extension is appended. For all other operating systems, a file extension suitable for the current executable file format is appended if no file extension is specified.

Consider the following example.

Example:

```
wlink system my_os name myprog file test, test2, test3
```

The linker is instructed to generate an executable file called "myprog.exe" if you are running a DOS, OS/2 or Windows-hosted version of the linker. If you are running a QNX-hosted version of the linker, an executable file called "myprog" will be generated.

Notes:

1. No file extension was given when the executable file name was specified. The linker assumes a file extension that depends on the format of the executable file being generated. If you are running a QNX-hosted version of the linker, no file extension will be assumed. The section entitled "The FORMAT Directive" on page 56 describes the "FORMAT" directive and how the file extension is chosen for each executable file format.
2. If no "NAME" directive is present, the executable file will have the file name of the first object file processed by the linker. If the first object file processed is called "test.obj" and no "NAME" directive is specified, an executable file called "test.exe" will be generated if you are running a DOS or OS/2-hosted version of the linker. If you are running a QNX-hosted version of the linker, an executable file called "test" will be generated.

3.50 The NAMELEN Option

Formats: All

The "NAMELEN" option tells the Watcom Linker that all symbols must be uniquely identified in the number of characters specified or less. If any symbol fails to satisfy this condition, a warning message will be issued. The warning message will state that a symbol has been defined more than once.

The format of the "NAMELEN" option (short form "NAMEL") is as follows.

<i>OPTION NAMELEN=n</i>

where **description:**

n represents a value. The complete form of *n* is the following.

[0x] d { d } [k | m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

Some computer systems, for example, require that all global symbols be uniquely identified in 8 characters. By specifying an appropriate value for the "NAMELEN" option, you can ease the task of porting your application to other computer systems.

3.51 The NEWFILES Option

Formats: OS/2

The "NEWFILES" option specifies that the application uses the high-performance file system. This option is applicable to 16-bit OS/2 applications only. The format of the "NEWFILES" option (short form "NEWF") is as follows.

<i>OPTION NEWFILES</i>

3.52 The *NEWSEGMENT* Directive

Formats: DOS, OS/2, QNX, Win16

This directive is intended for 16-bit segmented applications. By default, the Watcom Linker automatically groups logical code segments into physical segments. By default, these segments are 64K bytes in size. However, the "PACKCODE" option can be used to specify a maximum size for all physical segments that is smaller than 64K bytes.

The "NEWSEGMENT" directive provides an alternate method of grouping code segments into physical segments. By placing this directive after a sequence of "FILE" directives, all code segments appearing in object modules specified by the sequence of "FILE" directives will be packed into a physical segment. Note that the size of a physical segment may vary in size. The format of the "NEWSEGMENT" directive (short form "NEW") is as follows.

<p><i>NEWSEGMENT</i></p>

Consider the following example.

```
file file1, file2, file3
newsegment
file file4
file file5
```

Code segments from *file1*, *file2* and *file3* will be grouped into one physical segment. Code segments from *file4* and *file5* will be grouped into another physical segment.

Note that code segments extracted from library files will be grouped into physical segments as well. The size of these physical segments is determined by the "PACKCODE" option and is 64k by default.

3.53 The NLMFLAGS Option

Formats: NetWare

The "NLMFLAGS" option is used to set bits in the flags field of the header of the Netware executable file. The format of the "NLMFLAGS" option (short form "NLMF") is as follows.

<i>OPTION NLMFLAGS=some_value</i>

where *description:*

some_value is an integer value that is OR'ed into the flags field of the header of the Netware executable.

3.54 The NOAUTODATA Option

Formats: OS/2, Win16

The "NOAUTODATA" option specifies that no automatic data segment (default data segment defined by the group "DGROUPE"), exists for the program module or Dynamic Link Library being created. This option applies to 16-bit applications only. The format of the "NOAUTODATA" option (short form "NOA") is as follows.

<i>OPTION NOAUTODATA</i>

3.55 The NODEFAULTLIBS Option

Formats: All

Special object module records that specify default libraries are placed in object files generated by Watcom compilers. These libraries reflect the memory and floating-point model that a source file was compiled for and are automatically searched by the Watcom Linker when unresolved symbols are detected. These libraries can exist in the current directory, in one of the paths specified in "LIBPATH" directives, or in one of the paths specified in the **LIB** environment variable.

Note that all library files that appear in a "LIBRARY" directive are searched before default libraries. The "NODEFAULTLIBS" option instructs the Watcom Linker to ignore default libraries. That is, only libraries appearing in a "LIBRARY" directive are searched.

The format of the "NODEFAULTLIBS" option (short form "NOD") is as follows.

<i>OPTION NODEFAULTLIBS</i>

3.56 The NORELOCS Option

Formats: QNX, Win32

The "NORELOCS" option specifies that no relocation information is to be written to the executable file. When the "NORELOCS" option is specified, the executable file can only be run in protected mode and will not run in real mode. In real mode, the relocation information is required; in protected mode, the relocation information is not required unless your application is running at privilege level 0.

The format of the "NORELOCS" option (short form "NOR") is as follows.

<i>OPTION NORELOCS</i>

where *description:*

NORELOCS tells the Watcom Linker not to generate relocation information.

3.57 The NOSTDCALL Option

Formats: Win32

The "NOSTDCALL" option specifies that the characters unique to the `__stdcall` calling convention be trimmed from all of the symbols that are exported from the DLL being created. The format of the "NOSTDCALL" option (short form "NOSTDC") is as follows.

OPTION NOSTDCALL

Considering the following declarations.

Example:

```
short PASCAL __export Function1( short var1,
                                long varlong,
                                short var2 );

short PASCAL __export Function2( long varlong,
                                short var2 );
```

Under ordinary circumstances, these `__stdcall` symbols are mapped to "_Function1@12" and "_Function2@8" respectively. The "@12" and "@8" reflect the number of bytes in the argument list (short is passed as int). When the "NOSTDCALL" option is specified, these symbols are stripped of the "_" and "@xx" adornments. Thus they are exported from the DLL as "Function1" and "Function2".

This option makes it easier to access functions exported from DLLs, especially when using other software languages such as FORTRAN which do not add on the `__stdcall` adornments.

Note: Use the "IMPLIB" option to create an import library for the DLL which can be used with software languages that add on the `__stdcall` adornments.

3.58 The OBJALIGN Option

Formats: Win32

The "OBJALIGN" option specifies the alignment for objects in the executable file. The format of the "OBJALIGN" option (short form "OBJA") is as follows.

<i>OPTION OBJALIGN=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

[0x] d { d } [k | m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n must be a value that is a power of 2 and is between 512 bytes and 256 megabytes inclusive. The default is 64k.

3.59 The *OLDLIBRARY* Option

Formats: OS/2, Win16, Win32

The "OLDLIBRARY" option is used to preserve the export ordinals for successive versions of a Dynamic Link Library. This ensures that any application that references functions in a Dynamic Link Library by ordinal will continue to execute correctly. The format of the "OLDLIBRARY" option (short form "OLD") is as follows.

<i>OPTION OLDLIBRARY=dll_name</i>

where *description:*

dll_name is a file specification for the name of a Dynamic Link Library. If no file extension is specified, a file extension of "DLL" is assumed.

Only the current directory or a specified directory will be searched for Dynamic Link Libraries specified in the "OLDLIBRARY" option.

3.60 The OFFSET Option

Formats: OS/2, PharLap, QNX, Win32

For OS/2 and Win32 applications, the "OFFSET" option specifies the preferred base linear address at which the executable or DLL will be loaded.

For 32-bit PharLap and QNX applications, the "OFFSET" option specifies the offset in the program's segment in which the first byte of code or data is loaded.

3.60.1 OFFSET - OS/2, Win32 only

The "OFFSET" option specifies the preferred base linear address at which the executable or DLL will be loaded. The Watcom Linker will relocate the application for the specified base linear address so that when it is loaded by the operating system, no relocation will be required. This decreases the load time of the application.

If the operating system is unable to load the application at the specified base linear address, it will load it at a different location which will increase the load time since a relocation phase must be performed.

The format of the "OFFSET" option (short form "OFF") is as follows.

<i>OPTION OFFSET=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

[0x] d { d } [k | m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

The "OFFSET" option is used to specify the base linear address (in bytes) at which the program is loaded and must be a multiple of 64K. The linker will round the value up to a multiple of 64K if it is not already a multiple of 64K. The default base linear address is 64K for OS/2 executables and 4096K for Win32 executables.

This option is most useful for improving the load time of DLLs, especially for an application that uses multiple DLLs.

3.60.2 OFFSET - PharLap only

The "OFFSET" option specifies the offset in the program's segment in which the first byte of code or data is loaded. The format of the "OFFSET" option (short form "OFF") is as follows.

<i>OPTION OFFSET=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

[0x] d { d } [k | m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n specifies the offset (in bytes) at which the program is loaded and must be a multiple of 4K. The Watcom Linker will round the value up to a multiple of 4K if it is not already a multiple of 4K.

It is possible to detect NULL pointer references by linking the program at an offset which is a multiple of 4K. Usually an offset of 4K is sufficient.

Example:

```
option offset=4k
```

When the program is loaded by 386|DOS-Extender, the pages skipped by the "OFFSET" option are not mapped. Any reference to an unmapped area (such as a NULL pointer) will cause a page fault preventing the NULL reference from corrupting the program.

3.60.3 OFFSET - QNX only

The "OFFSET" option specifies the offset in the program's segment in which the first byte of code or data is loaded. This option does not apply to 16-bit QNX applications. The format of the "OFFSET" option (short form "OFF") is as follows.

<i>OPTION OFFSET=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

[0x] d { d } [k | m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n specifies the offset (in bytes) at which the program is loaded and must be a multiple of 4K. The Watcom Linker will round the value up to a multiple of 4K if it is not already a multiple of 4K. The following describes a use of the "OFFSET" option.

It is possible to detect NULL pointer references by linking the program at an offset which is a multiple of 4K. Usually an offset of 4K is sufficient.

Example:

```
option offset=4k
```

When the program is loaded, the pages skipped by the "OFFSET" option are not mapped. Any reference to an unmapped area (such as a NULL pointer) will cause a page fault preventing the NULL reference from corrupting the program.

3.61 The ONEAUTODATA Option

Formats: OS/2, Win16

The "ONEAUTODATA" option specifies that the automatic data segment (default data segment defined by the group "DGROUP"), for the program module or Dynamic Link Library (DLL) being created, will be shared by all instances. The format of the "ONEAUTODATA" option (short form "ONE") is as follows.

<i>OPTION ONEAUTODATA</i>

The default for a Dynamic Link Library is "ONEAUTODATA" and for a program module is "MANYAUTODATA". If you do not want the data area of a DLL to be shared across multiple applications, then you should specify "OPTION MANYAUTODATA".

Win16: Note, however, that this attribute is not supported by Windows 3.x for 16-bit DLLs.

You should also see the related section entitled "The FORMAT Directive" on page 56 for information on the "INITINSTANCE", "TERMINSTANCE", "INITGLOBAL", and "TERMGLOBAL" DLL attributes.

3.62 The *OPTION* Directive

Formats: All

The "OPTION" directive is used to specify options to the Watcom Linker. The format of the "OPTION" directive (short form "OP") is as follows.

<i>OPTION option{,option}</i>

where *description:*

option is any of the linker options available for the executable format that is being generated.

3.63 The OPTLIB Directive

Formats: All

The "OPTLIB" directive is used to specify the library files to be searched when unresolved symbols remain after processing all specified input object files. The format of the "OPTLIB" directive (no short form) is as follows.

OPTLIB library_file{,library_file}

where *description:*

library_file is a file specification for the name of a library file. If no file extension is specified, a file extension of "lib" is assumed.

This directive is similar to the "LIBRARY" directive except that the linker will not issue a warning message if the library file cannot be found.

Consider the following example.

Example:

```
wlink system my_os file trig optlib \math\trig, \cplx\trig
```

The Watcom Linker is instructed to process the following object file:

```
trig.obj
```

If any unresolved symbol references remain after all object files have been processed, the following library files will be searched:

```
\math\trig.lib  
\cplx\trig.lib
```

More than one "OPTLIB" directive may be used. The following example is equivalent to the preceding one.

Example:

```
wlink system my_os f trig optlib \math\trig optlib
\cplx\trig
```

Thus other directives may be placed between lists of library files.

3.63.1 Searching for Optional Libraries Specified in Environment Variables

The "LIB" environment variable can be used to specify a list of paths that will be searched for library files. The "LIB" environment variable can be set using the "set" command as follows:

```
set lib=\graphics\lib;\utility
```

Consider the following "OPTLIB" directive and the above definition of the "LIB" environment variable.

```
optlib \mylibs\util, graph
```

If undefined symbols remain after processing all object files specified in all "FILE" directives, the Watcom Linker will resolve these references by searching the following libraries in the specified order.

1. the library file "\mylibs\util.lib"
2. the library file "graph.lib" in the current directory
3. the library file "\graphics\lib\graph.lib"
4. the library file "\utility\graph.lib"

Notes:

1. If a library file specified in a "OPTLIB" directive contains an absolute path specification, the Watcom Linker will not search any of the paths specified in the "LIB" environment string for the library file. On QNX-hosted systems, an absolute path specification is one that begins the "/" character. On all other hosts, an absolute path specification is one that begins with a drive specification or the "\" character.
2. Once a library file has been found, no further elements of the "LIB" environment variable are searched for other libraries of the same name. That is, if the library file "\graphics\lib\graph.lib" exists, the library file "\utility\graph.lib" will not be searched even though unresolved references may remain.

3.64 The OSDOMAIN Option

Formats: NetWare

The "OSDOMAIN" option is used when the application is to run in the operating system domain (ring 0).

The format of the "OSDOMAIN" option (short form "OSD") is as follows.

<i>OPTION OSDOMAIN</i>

3.65 The PSEUDOPREEMPTION Option

Formats: NetWare

The "PSEUDOPREEMPTION" option specifies that an additional set of system calls will yield control to other processes. Multitasking in the NetWare 386 operating system is non-preemptive. That is, a process must give up control in order for other processes to execute. Using the "PSEUDOPREEMPTION" option increases the probability that all processes are given an equal amount of CPU time.

The format of the "PSEUDOPREEMPTION" option (short form "PS") is as follows.

<i>OPTION PSEUDOPREEMPTION</i>

3.66 The OSNAME Option

Formats: All

The "OSNAME" option can be used to set the name of the target operating system of the executable file generated by the linker. The format of the "OSNAME" option (short form "OSN") is as follows.

```
OPTION OSNAME='string'
```

where *description:*

string is any sequence of characters.

The information specified by the "OSNAME" option will be displayed in the *creating a ? executable* message. This is the last line of output produced by the linker, provided the "QUIET" option is not specified. Consider the following example.

```
option osname='SuperOS'
```

The last line of output produced by the linker will be as follows.

```
creating a SuperOS executable
```

Some executable formats have a stub executable file that is run under 16-bit DOS. The message displayed by the default stub executable file will be modified when the "OSNAME" option is used. The default stub executable displays the following message:

OS/2: this is an OS/2 executable

Win16: this is a Windows executable

Win32: this is a Windows NT executable

If the "OSNAME" option used in the previous example was specified, the default stub executable would generate the following message.

```
this is a SuperOS executable
```

3.67 The *PACKCODE* Option

Formats: DOS, OS/2, QNX, Win16

This option is intended for 16-bit segmented applications. By default, the Watcom Linker automatically groups logical code segments into physical segments. The "PACKCODE" option is used to specify the size of the physical segment. The format of the "PACKCODE" option (short form "PACKC") is as follows.

<i>OPTION PACKCODE=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

[0x] d { d } [k | m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n specifies the size of the physical segments into which code segments are packed. The default value of *n* is 64K for 16-bit applications. Note that this is also the maximum size of a physical segment. To suppress automatic grouping of code segments, specify a value of 0 for *n*.

Notes:

1. Only adjacent segments are packed into a physical segment.
2. Segments belonging to the same group are packed in a physical segment. Segments belonging to different groups are not packed into a physical segment.
3. Segments with different attributes are not packed together unless they are explicitly grouped.

3.68 The PACKDATA Option

Formats: DOS, OS/2, QNX, Win16

This option is intended for 16-bit segmented applications. By default, the Watcom Linker automatically groups logical far data segments into physical segments. The "PACKDATA" option is used to specify the size of the physical segment. The format of the "PACKDATA" option (short form "PACKD") is as follows.

<i>OPTION PACKDATA=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

$$[0x]d\{d\}[k|m]$$

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

n specifies the size of the physical segments into which far data segments are packed. The default value of *n* is 64K for 16-bit applications. Note that this is also the maximum size of a physical segment. To suppress automatic grouping of far data segments, specify a value of 0 for *n*.

Notes:

1. Only adjacent segments are packed into a physical segment.
2. Segments belonging to the same group are packed in a physical segment. Segments belonging to different groups are not packed into a physical segment.
3. Segments with different attributes are not packed together unless they are explicitly grouped.

3.69 The PATH Directive

Formats: All

The "PATH" directive is used to specify the directories that are to be searched for object files appearing in subsequent "FILE" directives. When the "PATH" directive is specified, the current directory will no longer be searched unless it appears in the "PATH" directive. The format of the "PATH" directive (short form "P") is as follows.

PATH path_name{;path_name}

where *description:*

path_name is a path name.

Consider a directive file containing the following linker directives.

```
path \math
file sin
path \stats
file mean, variance
```

It instructs the Watcom Linker to process the following object files:

```
\math\sin.obj
\stats\mean.obj
\stats\variance.obj
```

It is also possible to specify a list of paths in a "PATH" directive. Consider the following example.

```
path \math;\stats
file sin
```

First, the linker will attempt to load the file "\math\sin.obj". If unsuccessful, the linker will attempt to load the file "\stats\sin.obj".

It is possible to override the path specified in a "PATH" directive by preceding the object file name in a "FILE" directive with an absolute path specification. On QNX-hosted systems, an absolute path specification is one that begins the "/" character. On all other hosts, an absolute path specification is one that begins with a drive specification or the "\" character.

```
path \math
file sin
path \stats
file mean, \mydir\variance
```

The above directive file instructs the linker to process the following object files:

```
\math\sin.obj
\stats\mean.obj
\mydir\variance.obj
```

3.70 The PRIVILEGE Option

Formats: QNX

The "PRIVILEGE" option specifies the privilege level (0, 1, 2 or 3) at which the application will run. The format of the "PRIVILEGE" option (short form "PRIV") is as follows.

<i>OPTION PRIVILEGE=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

[0x] d { d } [k | m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

The default privilege level is 0.

3.71 The PROTMODE Option

Formats: OS/2

The "PROTMODE" option specifies that the application will only run in protected mode. This option applies to 16-bit OS/2 applications only. The format of the "PROTMODE" option (short form "PROT") is as follows.

<i>OPTION PROTMODE</i>

3.72 The QUIET Option

Formats: All

The "QUIET" option tells the Watcom Linker to suppress all informational messages. Only warning, error and fatal messages will be issued. By default, the Watcom Linker issues informational messages. The format of the "QUIET" option (short form "Q") is as follows.

<i>OPTION QUIET</i>

3.73 The REDEFSOK Option

Formats: All

The "REDEFSOK" option tells the Watcom Linker to ignore redefined symbols and to generate an executable file anyway. By default, warning messages are displayed and an executable file is generated if redefined symbols are present.

The format of the "REDEFSOK" option (short form "RED") is as follows.

<i>OPTION REDEFSOK</i>

The "NOREDEFSOK" option tells the Watcom Linker to treat redefined symbols as an error and to not generate an executable file. By default, warning messages are displayed and an executable file is generated if redefined symbols are present.

The format of the "NOREDEFSOK" option (short form "NORED") is as follows.

<i>OPTION NOREDEFSOK</i>

3.74 The REENTRANT Option

Formats: NetWare

The "REENTRANT" option specifies that the module is reentrant. That is, if an NLM is LOADED twice, the actual code in the server's memory is reused. The NLM's start procedure is called once for each LOAD. The format of the "REENTRANT" option (short form "RE") is as follows.

<i>OPTION REENTRANT</i>

3.75 The REFERENCE Directive

Formats: All

The "REFERENCE" directive is used to explicitly reference a symbol that is not referenced by any object file processed by the linker. If any symbol appearing in a "REFERENCE" directive is not resolved by the linker, an error message will be issued for that symbol specifying that the symbol is undefined.

The "REFERENCE" directive can be used to force object files from libraries to be linked with the application. Also note that a symbol appearing in a "REFERENCE" directive will not be eliminated by dead code elimination. For more information on dead code elimination, see the section entitled "The ELIMINATE Option" on page 47.

The format of the "REFERENCE" directive (short form "REF") is as follows.

REFERENCE *symbol_name*{, *symbol_name*}

where *description:*

symbol_name is the symbol for which a reference is made.

Consider the following example.

```
reference domino
```

The symbol `domino` will be searched for. The object module that defines this symbol will be linked with the application. Note that the linker will also attempt to resolve symbols referenced by this module.

3.76 The RESOURCE Option

Formats: OS/2, QNX, Win16, Win32

For 16-bit OS/2 executable files and Win16 or Win32 executable files, the "RESOURCE" option requests the linker to add the specified resource file to the executable file being generated. For QNX executable files, the "RESOURCE" option specifies the contents of the resource record.

3.76.1 RESOURCE - OS/2, Win16, Win32 only

The "RESOURCE" option requests the linker to add the specified resource file to the executable file that is being generated. The format of the "RESOURCE" option (short form "RES") is as follows.

*OPTION RESOURCE[=*resource_file*]*

where *description:*

resource_file is a file specification for the name of the resource file that is to be added to the executable file. If no file extension is specified, a file extension of "RES" is assumed for all but QNX format executables.

The "RESOURCE" option cannot be used for 32-bit OS/2 executables.

3.76.2 RESOURCE - QNX only

The "RESOURCE" option specifies the contents of the resource record in QNX executable files. The format of the "RESOURCE" option (short form "RES") is as follows.

OPTION RESOURCE resource_info

resource_info ::= 'string' | =resource_file

where *description:*

resource_file is a file specification for the name of the resource file. No file extension is assumed.

string is a sequence of characters which is placed in the resource record.

If a resource file is specified, the contents of the resource file are included in the resource record.

The resource record contains, for example, help information and is displayed when the following command is executed.

```
use <executable>
```

QNX also provides the **usemsg** utility to manipulate the resource record of an executable file. Its use is recommended. This utility is described in the QNX "Utilities Reference" manual.

3.77 The RUNTIME Directive

Formats: PharLap, Win32

For Win32 applications, the "RUNTIME" directive specifies the environment under which the application will run.

For PharLap applications, the "RUNTIME" directive describes information that is used by 386DOS-Extender to setup the environment for execution of the program.

3.77.1 RUNTIME - Win32 only

The "RUNTIME" directive specifies the environment under which the application will run. The format of the "RUNTIME" directive (short form "RU") is as follows.

```
RUNTIME env[=major[.minor]]
```

```
env ::= NATIVE / WINDOWS / CONSOLE / POSIX / OS2 / DOSSTYLE
```

where *description:*

env=major.minor Specifying a system version in the form "major" or "major.minor" indicates the minimum operating system version required for the application. For example, the following indicates that the application requires Windows 95.

```
runtime windows=4.0
```

NATIVE (short form "NAT") indicates that the application is a native Windows NT application.

WINDOWS (short form "WIN") indicates that the application is a Windows application.

CONSOLE (short form "CON") indicates that the application is a character-mode (command line oriented) application.

POSIX (short form "POS") indicates that the application uses the POSIX subsystem available with Windows NT.

OS2 indicates that the application is a 16-bit OS/2 1.x application.

DOSSTYLE (short form "DOS") indicates that the application is a Phar Lap TNT DOS extender application that uses INT 21 to communicate to the DOS extender rather than calls to a DLL.

3.77.2 RUNTIME - PharLap only

The "RUNTIME" directive describes information that is used by 386|DOS-Extender to setup the environment for execution of the program. The format of the "RUNTIME" directive (short form "RU") is as follows.

```
RUNTIME run_option{run_option}
```

```
run_option ::= MINREAL=n / MAXREAL=n / CALLBUFS=n / MINIBuf=n  
/ MAXIBUF=n / NISTACK=n / ISTKSIZE=n  
/ REALBREAK=offset / PRIVILEGED / UNPRIVILEGED
```

```
offset ::= n / symbol_name
```

where *description:*

n represents a value. The complete form of *n* is the following.

```
[ 0x ] d { d } [ k | m ]
```

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

symbol_name is a symbol name.

MINREAL (short form "MINR") specifies the minimum number of bytes of conventional memory required to be free after a program is loaded by 386|DOS-Extender. Note that this memory is no longer available to the executing program. The default value of *n* is 0 in which case 386|DOS-Extender allocates all conventional memory for the executing program. The Watcom Linker truncates the specified value to a multiple of 16. *n* must be less than or equal to hexadecimal 100000 (64K*16).

MAXREAL (short form "MAXR") specifies the maximum number of bytes of conventional memory than can be left free after a program is loaded by 386|DOS-Extender. Note that this memory is not available to the executing program. The default

value of n is 0 in which case 386|DOS-Extender allocates all conventional memory for the executing program. n must be less than or equal to hexadecimal ffff0. The Watcom Linker truncates the specified value to a multiple of 16.

CALLBUFS (short form "CALLB") specifies the size of the call buffer allocated for switching between 32-bit protected mode and real mode. This buffer is used for communicating information between real-mode and 32-bit protected-mode procedures. The buffer address is obtained at run-time with a 386|DOS-Extender system call. The size returned is the size of the buffer in kilobytes and is less than or equal to 64.

The default buffer size is zero unless changed using the "CALLBUFS" option. The Watcom Linker truncates the specified value to a multiple of 1024. n must be less than or equal to 64K. Note that n is the number of bytes, not kilobytes.

MINIBUF (short form "MINIB") specifies the minimum size of the data buffer that is used when DOS and BIOS functions are called. The size of this buffer is particularly important for file I/O. If your program reads or writes large amounts of data, a large value of n should be specified. n represents the number of bytes and must be less than or equal to 64K. The default value of n is 1K. The Watcom Linker truncates the specified value to a multiple of 1024.

MAXIBUF (short form "MAXIB") specifies the maximum size of the data buffer that is used when DOS and BIOS functions are called. The size of this buffer is particularly important for file I/O. If your program reads or writes large amounts of data, a large value of n should be specified. n represents the number of bytes and must be less than or equal to 64K. The default value of n is 4K. The Watcom Linker truncates the specified value to a multiple of 1024.

NISTACK (short form "NIST") specifies the number of stack buffers to be allocated for use by 386|DOS-Extender when switching from 32-bit protected mode to real mode. By default, 4 stack buffers are allocated. n must be greater than or equal to 4.

ISTKSIZE (short form "ISTK") specifies the size of the stack buffers allocated for use by 386|DOS-Extender when switching from 32-bit protected mode to real mode. By default, the size of a stack buffer is 1K. The value of n must be greater than or equal to 1K and less than or equal to 64K. The Watcom Linker truncates the specified value to a multiple of 1024.

REALBREAK (short form "REALB") specifies how much of the program must be loaded into conventional memory so that it can be accessed and/or executed in real mode. If n is specified, the first n bytes of the program must be loaded into conventional memory. If *symbol* is specified, all bytes up to but not including the symbol must be loaded into conventional memory.

PRIVILEGED (short form "PRIV") specifies that the executable is to run at Ring 0 privilege level.

UNPRIVILEGED (short form "UNPRIV") specifies that the executable is to run at Ring 3 privilege level (i.e., unprivileged). This is the default privilege level.

3.78 The RWRELOCHECK Option

Formats: Win16

The "RWRELOCHECK" option causes the linker to check for segment relocations to a read/write data segment and issue a warning if any are found. This option is useful if you are building a 16-bit Windows application that may have more than one instance running at a given time.

The format of the "RWRELOCHECK" option (short form "RWR") is as follows.

<i>OPTION RWRELOCHECK</i>

3.79 The SCREENNAME Option

Formats: NetWare

The "SCREENNAME" option specifies the name of the first screen (the screen that is automatically created when an NLM is loaded). The format of the "SCREENNAME" option (short form "SCR") is as follows.

<i>OPTION SCREENNAME 'name'</i>

where *description:*

name specifies the screen name.

If the "SCREENNAME" option is not specified, the *description* text specified in the "FORMAT" directive is used as the screen name.

3.80 The SEGMENT Directive

Formats: OS/2, QNX, Win16, Win32

The "SEGMENT" directive is used to describe the attributes of code and data segments. The format of the "SEGMENT" directive (short form "SEG") is as follows.

```
SEGMENT seg_desc{,seg_desc}  
  
seg_desc ::= seg_id {seg_attrs}+  
  
seg_id ::= 'seg_name' / CLASS 'class_name' / TYPE [CODE / DATA]
```

OS/2:

```
seg_attrs ::= PRELOAD / LOADONCALL  
          / IOPL / NOIOPL  
          / EXECUTEONLY / EXECUTEREAD  
          / READONLY / READWRITE  
          / SHARED / NONSHARED  
          / CONFORMING / NONCONFORMING  
          / PERMANENT / NONPERMANENT  
          / INVALID / RESIDENT  
          / CONTIGUOUS / DYNAMIC
```

Win32:

```
seg_attrs ::= PAGEABLE / NONPAGEABLE  
          / SHARED / NONSHARED
```

Win16:

```
seg_attrs ::= PRELOAD / LOADONCALL  
          / EXECUTEONLY / EXECUTEREAD  
          / READONLY / READWRITE  
          / SHARED / NONSHARED  
          / MOVEABLE / FIXED  
          / DISCARDABLE
```

QNX:

```
seg_attrs ::= EXECUTEONLY / EXECUTEREAD  
          / READONLY / READWRITE
```

<i>where</i>	<i>description:</i>
<i>seg_name</i>	is the name of the code or data segment whose attributes are being specified.
<i>class_name</i>	is a class name. The attributes will be assigned to all segments belonging to the specified class.
PRELOAD	(short form "PR", OS/2 and Win16 only) specifies that the segment is loaded as soon as the executable file is loaded. This is the default.
LOADONCALL	(short form "LO", OS/2 and Win16 only) specifies that the segment is loaded only when accessed.
PAGEABLE	(short form "PAGE", Win32 only) specifies that the segment can be paged from memory. This is the default.
NONPAGEABLE	(short form "NONP", Win32 only) specifies that the segment, once loaded into memory, must remain in memory.
CONFORMING	(short form "CON", OS/2 only) specifies that the segment will assume the I/O privilege of the segment that referenced it. By default, the segment is "NONCONFORMING".
NONCONFORMING	(short form "NONC", OS/2 only) specifies that the segment will not assume the I/O privilege of the segment that referenced it. This is the default.
IOPL	(short form "I", OS/2 only) specifies that the segment requires I/O privilege. That is, they can access the hardware directly.
NOIOPL	(short form "NOI", OS/2 only) specifies that the segment does not require I/O privilege. This is the default.
PERMANENT	(short form "PERM", OS/2 32-bit only) specifies that the segment is permanent.
NONPERMANENT	(short form "NONPERM", OS/2 32-bit only) specifies that the segment is not permanent.
INVALID	(short form "INV", OS/2 32-bit only) specifies that the segment is invalid.
RESIDENT	(short form "RES", OS/2 32-bit only) specifies that the segment is resident.
CONTIGUOUS	(short form "CONT", OS/2 32-bit only) specifies that the segment is contiguous.

SEGMENT (OS/2, QNX, Win16, Win32)

DYNAMIC (short form "DYN", OS/2 32-bit only) specifies that the segment is dynamic.

EXECUTEONLY (short form "EXECUTEO", OS/2, QNX and Win16 only) specifies that the segment can only be executed. This attribute should only be specified for code segments. This attribute should not be specified if it is possible for the code segment to contain jump tables which is the case with the Watcom C, C++ and FORTRAN 77 optimizing compilers.

EXECUTEREAD (short form "EXECUTER", OS/2, QNX and Win16 only) specifies that the segment can only be executed and read. This attribute, the default for code segments, should only be specified for code segments. This attribute is appropriate for code segments that contain jump tables as is possible with the Watcom C, C++ and FORTRAN 77 optimizing compilers.

READONLY (short form "READO", OS/2, QNX and Win16 only) specifies that the segment can only be read. This attribute should only be specified for data segments.

READWRITE (short form "READW", OS/2, QNX and Win16 only) specifies that the segment can be read and written. This is the default for data segments. This attribute should only be specified for data segments.

SHARED (short form "SH") specifies that a single copy of the segment will be loaded and will be shared by all processes.

NONSHARED (short form "NONS") specifies that a unique copy of the segment will be loaded for each process. This is the default.

MOVEABLE (short form "MOV", Win16 only) specifies that the segment is moveable. By default, segments are moveable.

FIXED (short form "FIX", Win16 only) specifies that the segment is fixed.

DISCARDABLE (short form "DIS", Win16 only) specifies that the segment is discardable. By default, segments are not discardable.

<p><i>Note:</i> Attributes specified for segments identified by a segment name override attributes specified for segments identified by a class name.</p>

3.81 The SHARELIB Option

Formats: NetWare

The "SHARELIB" option specifies the file name of an NLM to be loaded as a shared NLM. Shared NLMs contain global code and global data that are mapped into all memory protection domains. This method of loading APIs can be used to avoid ring transitions to call other APIs in other domains.

The format of the "SHARELIB" option (short form "SHA") is as follows.

<i>OPTION SHARELIB=shared_nlm</i>

where *description:*

shared_nlm is the file name of the shared NLM.

3.82 The *SHOWDEAD* Option

Formats: All

The "SHOWDEAD" option instructs the linker to list, in the map file, the symbols associated with dead code and unused C++ virtual functions that it has eliminated from the link. The format of the "SHOWDEAD" option (short form "SHO") is as follows.

<i>OPTION SHOWDEAD</i>

The "SHOWDEAD" option works best in concert with the "ELIMINATE" and "VFREMOVAL" options.

3.83 The SORT Directive

Formats: All

The "SORT" directive is used to sort the symbols in the "Memory Map" section of the map file. By default, symbols are listed on a per module basis in the order the modules were encountered by the linker. That is, a module header is displayed followed by the symbols defined by the module.

The format of the "SORT" directive (short form "SO") is as follows.

```
SORT [GLOBAL] [ALPHABETICAL]
```

If the "SORT" directive is specified without any options, as in the following example, the module headers will be displayed each followed by the list of symbols it defines sorted by address.

```
sort
```

If only the "GLOBAL" sort option (short form "GL") is specified, as in the following example, the module headers will not be displayed and all symbols will be sorted by address.

```
sort global
```

If only the "ALPHABETICAL" sort option (short form "ALP") is specified, as in the following example, the module headers will be displayed each followed by the list of symbols it defines sorted alphabetically.

```
sort alphabetical
```

If both the "GLOBAL" and "ALPHABETICAL" sort options are specified, as in the following example, the module headers will not be displayed and all symbols will be sorted alphabetically.

```
sort global alphabetical
```

If you are linking a Watcom C++ application, mangled names are sorted by using the base name. The base name is the name of the symbol as it appeared in the source file. See the section entitled "The MANGLEDNAMES Option" on page 87 for more information on mangled names.

3.84 The STACK Option

Formats: All

The "STACK" option can be used to increase the size of the stack. The format of the "STACK" option (short form "ST") is as follows.

<i>OPTION STACK=n</i>

where *description:*

n represents a value. The complete form of *n* is the following.

[0x]d{d}[k|m]

d represents a decimal digit. If *0x* is specified, the string of digits represents a hexadecimal number. If *k* is specified, the value is multiplied by 1024. If *m* is specified, the value is multiplied by 1024*1024.

The default stack size varies for both 16-bit and protected-mode 32-bit applications depending on the executable format. You can determine the default stack size by looking at the map file that can be generated when an application is linked ("OPTION MAP"). During execution of your program, you may get an error message indicating your stack has overflowed. If you encounter such an error, you must link your application again, this time specifying a larger stack size using the "STACK" option.

Example:

```
option stack=8192
```

3.85 The START Option

Formats: All

The format of the "START" option is as follows.

<i>OPTION START=</i> <i>symbol_name</i>

where *description:*

symbol_name specifies the name of the procedure where execution begins.

For the Netware 386 executable format, the default name of the start procedure is "_Prelude".

3.86 The STARTLINK Directive

Formats: All

The "STARTLINK" directive is used to indicate the start of a new set of linker commands that are to be processed after the current set of commands has been processed. The format of the "STARTLINK" directive (short form "STARTL") is as follows.

<i>STARTLINK</i>

The "ENDLINK" directive is used to indicate the end of the set of commands identified by the "STARTLINK" directive.

3.87 The STATICS Option

Formats: All

The "STATICS" option should only be used if you are developing a Watcom C or C++ application. The Watcom C and C++ compilers produce definitions for static symbols in the object file. By default, these static symbols do not appear in the map file. If you want static symbols to be displayed in the map file, use the "STATICS" option.

The format of the "STATICS" option (short form "STAT") is as follows.

<i>OPTION STATICS</i>

3.88 The STUB Option

Formats: OS/2, Win16, Win32

The "STUB" option specifies an executable file containing a "stub" program that is to be placed at the beginning of the executable file being generated. The "stub" program will be executed if the module is executed under DOS. The format of the "STUB" option is as follows.

<i>OPTION STUB=stub_name</i>

where *description:*

stub_name is a file specification for the name of the stub executable file. If no file extension is specified, a file extension of "EXE" is assumed.

The Watcom Linker will search all paths specified in the **PATH** environment variable for the stub executable file. The stub executable file specified by the "STUB" option must not be the same as the executable file being generated.

3.89 The SYMFILE Option

Formats: All

The "SYMFILE" option provides a method for specifying an alternate file for debugging information. The format of the "SYMFILE" option (short form "SYMF") is as follows.

*OPTION SYMFILE[=*symbol_file*]*

where *description:*

symbol_file is a file specification for the name of the symbol file. If no file extension is specified, a file extension of "sym" is assumed.

By default, no symbol file is generated; debugging information is appended at the end of the executable file. Specifying this option causes the Watcom Linker to generate a symbol file. The symbol file contains the debugging information generated by the linker when the "DEBUG" directive is used. The symbol file can then be used by Watcom Debugger. If no debugging information is requested, no symbol file is created, regardless of the presence of the "SYMFILE" option.

If no file name is specified, the symbol file will have a default file extension of "sym" and the same path and file name as the executable file. Note that the symbol file will be placed in the same directory as the executable file.

Alternatively, a file name can be specified. The following directive instructs the linker to generate a symbol file and call it "myprog.sym" regardless of the name of the executable file.

```
option symf=myprog
```

You can also specify a path and/or file extension when using the "SYMFILE=" form of the "SYMFILE" option.

Notes:

1. This option should be used to debug a DOS "COM" executable file. A DOS "COM" executable file must not contain any additional information other than the executable information itself since DOS uses the size of the file to determine what to load.

2. This option should be used when creating a Microsoft Windows executable file. Typically, before an executable file can be executed as a Microsoft Windows application, a resource compiler takes the Windows executable file and a resource file as input and combines them. If the executable file contains debugging information, the resource compiler will strip the debugging information from the executable file. Therefore, debugging information must not be part of the executable file created by the linker.

3.90 The SYMTRACE Directive

Formats: All

The "SYMTRACE" directive instructs the Watcom Linker to print a list of all modules that reference the specified symbols. The format of the "SYMTRACE" directive (short form "SYMT") is as follows.

SYMTRACE symbol_name{,symbol_name}

where *description:*

symbol_name is the name of a symbol.

The information is displayed in the map file. Consider the following example.

Example:

```
wlink system my_os op map file test lib math symt sin, cos
```

The Watcom Linker will list, in the map file, all modules that reference the symbols "sin" and "cos".

3.91 The SYNCHRONIZE Option

Formats: NetWare

The "SYNCHRONIZE" option forces an NLM to complete loading before starting to load other NLMs. Normally, the other NLMs are loading during the startup procedure. The format of the "SYNCHRONIZE" option (short form "SY") is as follows.

<i>OPTION SYNCHRONIZE</i>

3.92 The SYSTEM Directive

Formats: All

There are three forms of the "SYSTEM" directive.

The first form of the "SYSTEM" directive (short form "SYS") is called a system definition directive. It allows you to associate a set of linker directives with a specified name called the *system name*. This set of linker directives is called a system definition block. The format of a system definition directive is as follows.

```
SYSTEM BEGIN system_name {directive} END
```

where *description:*

system_name is a unique system name.

directive is a linker directive.

A system definition directive cannot be specified within another system definition directive.

The second form of the "SYSTEM" directive is called a system deletion directive. It allows you to remove the association of a set of linker directives with a *system name*. The format of a system deletion directive is as follows.

```
SYSTEM DELETE system_name
```

where *description:*

system_name is a defined system name.

The third form of the "SYSTEM" directive is as follows.

SYSTEM system_name

where *description:*

system_name is a defined system name.

When this form of the "SYSTEM" directive is encountered, all directives specified in the system definition block identified by *system_name* will be processed.

Let us consider an example that demonstrates the use of the "SYSTEM" directive. The following linker directives define a system called *statistics*.

```
system begin statistics
format dos
libpath \libs
library stats, graphics
option stack=8k
end
```

They specify that a *statistics* application is to be created by using the libraries "stats.lib" and "graphics.lib". These library files are located in the directory "\libs". The application requires a stack size of 8k and the specified format of executable will be generated.

Suppose the linker directives in the above example are contained in the file "stats.lnk". If we wish to create a *statistics* application, we can issue the following command.

```
wlink @stats system statistics file myappl
```

As demonstrated by the above example, the "SYSTEM" directive can be used to localize the common attributes that describe a class of applications.

The system deletion directive can be used to redefine a previously defined system. Consider the following example.

```
system begin at_dos
  libpath %WATCOM%\lib286
  libpath %WATCOM%\lib286\dos
  format dos ^
end
system begin n98_dos
  sys at_dos ^
  libpath %WATCOM%\lib286\dos\n98
end
system begin dos
  sys at_dos ^
end
```

If you wish to redefine the definition of the "dos" system, you can specify the following set of directives.

```
system delete dos
system begin dos
  sys n98_dos ^
end
```

This effectively redefines a "dos" system to be equivalent to a "n98_dos" system (NEC PC-9800 DOS), rather than the previously defined "at_dos" system (AT-compatible DOS).

For additional examples on the use of the "SYSTEM" directive, examine the contents of the `WLINK.LNK` and `WLSYSTEM.LNK` files.

The file `WLINK.LNK` is a special linker directive file that is automatically processed by the Watcom Linker before processing any other directives. On a DOS, OS/2, or Windows-hosted system, this file must be located in one of the paths specified in the **PATH** environment variable. On a QNX-hosted system, this file should be located in the `/etc` directory. A default version of this file is located in the `\WATCOM\BINW` directory on DOS-hosted systems, the `\WATCOM\BINP` directory on OS/2-hosted systems, the `/etc` directory on QNX-hosted systems, and the `\WATCOM\BINNT` directory on Windows 95 or Windows NT-hosted systems. Note that the file `WLINK.LNK` includes the file `WLSYSTEM.LNK` which is located in the `\WATCOM\BINW` directory on DOS, OS/2, or Windows-hosted systems and the `/etc` directory on QNX-hosted systems.

The files `WLINK.LNK` and `WLSYSTEM.LNK` reference the **WATCOM** environment variable which must be set to the directory in which you installed your software.

3.92.1 Special System Names

There are two special system names. When the linker has processed all object files and the executable file format has not been determined, and a system definition block has not been processed, the directives specified in the "286" or "386" system definition block will be processed. The "386" system definition block will be processed if a 32-bit object file has been processed. Furthermore, only a restricted set of linker directives is allowed in a "286" and "386" system definition block. They are as follows.

- FORMAT
- LIBFILE
- LIBPATH
- LIBRARY
- NAME
- OPTION
- RUNTIME (for Phar Lap executable files only)
- SEGMENT (for OS/2 and QNX executable files only)

3.93 The THREADNAME Option

Formats: NetWare

The "THREADNAME" option is used to specify the pattern to be used for generating thread names. The format of the "THREADNAME" option (short form "THR") is as follows.

<i>OPTION THREADNAME 'thread_name'</i>
--

where *description:*

thread_name specifies the pattern used for generating thread names and must be a string of 1 to 5 characters.

The first thread name is generated by appending "0" to *thread_name*, the second by appending "1" to *thread_name*, etc. If the "THREADNAME" option is not specified, the first 5 characters of the description specified in the "FORMAT" directive are used as the pattern for generating thread names.

3.94 The TOGGLERELOCS Option

Formats: OS/2

The "TOGGLERELOCS" option is used with LX format executables under 32-bit DOS/4G only. The "INTERNALRELOCS" option causes the Watcom Linker to include internal relocation information in DOS/4G LX format executables. Having done so, the linker normally clears the "internal fixups done" flag in the LX executable header (bit 0x10). The "TOGGLERELOCS" option causes the linker to toggle the value of the "internal fixups done" flag in the LX executable header (bit 0x10). This option is used with DOS/4G non-zero based executables. Contact Tenberry Software for further explanation.

The format of the "TOGGLERELOCS" option (short form "TOG") is as follows.

<i>OPTION TOGGLERELOCS</i>

3.95 The UNDEFSOK Option

Formats: All

The "UNDEFSOK" option tells the Watcom Linker to generate an executable file even if undefined symbols are present. By default, no executable file will be generated if undefined symbols are present.

The format of the "UNDEFSOK" option (short form "U") is as follows.

<i>OPTION UNDEFSOK</i>

The "NOUNDEFSOK" option tells the Watcom Linker to not generate an executable file if undefined symbols are present. This is the default behaviour.

The format of the "NOUNDEFSOK" option (short form "NOU") is as follows.

<i>OPTION NOUNDEFSOK</i>

3.96 The VERBOSE Option

Formats: All

The "VERBOSE" option controls the amount of information produced by the Watcom Linker in the map file. The format of the "VERBOSE" option (short form "V") is as follows.

<i>OPTION VERBOSE</i>

If the "VERBOSE" option is specified, the linker will list, for each object file, all segments it defines and their sizes. By default, this information is not produced in the map file.

3.97 The VERSION Option

Formats: NetWare, OS/2, Win16, Win32

The "VERSION" option can be used to identify the application so that it can be distinguished from other versions (releases) of the same application.

This option is most useful when creating a DLL or NLM since applications that use the DLL or NLM may only execute with a specific version of the DLL or NLM.

The format of the "VERSION" option (short form "VERS") is as follows.

<p><i>OS/2, Win16, Win32:</i> OPTION VERSION=<i>major[.minor]</i></p> <p><i>Netware:</i> OPTION VERSION=<i>major[.minor[.revision]]</i></p>

<i>where</i>	<i>description:</i>
<i>major</i>	specifies the major version number.
<i>minor</i>	specifies the minor version number and must be less than 100.
<i>revision</i>	specifies the revision. The revision should be a number or a letter. If it is a number, it must be less than 27.

3.98 The VFREMOVAL Option

Formats: All

The "VFREMOVAL" option instructs the linker to remove unused C++ virtual functions. The format of the "VFREMOVAL" option (short form "VFR") is as follows.

<i>OPTION VFREMOVAL</i>

If the "VFREMOVAL" option is specified, the linker will attempt to eliminate unused virtual functions. In order for the linker to do this, the Watcom C++ "zv" compiler option must be used for *all* object files in the executable. The "VFREMOVAL" option works best in concert with the "ELIMINATE" option.

3.99 The XDCDATA Option

Formats: NetWare

The "XDCDATA" option specifies the name of a file that contains Remote Procedure Call (RPC) descriptions for calls in this NLM. RPC descriptions for APIs make it possible for APIs to be exported across memory-protection domain boundaries.

The format of the "XDCDATA" option (short form "XDC") is as follows.

<i>OPTION XDCDATA=rpc_file</i>

where *description:*

rpc_file is the name of the file containing RPC descriptions.

4 The DOS Executable File Format

This chapter deals specifically with aspects of DOS executable files. The DOS executable file format will only run under the DOS operating system.

Input to the Watcom Linker is specified on the command line and can be redirected to one or more files or environment strings. The Watcom Linker command line format is as follows.

WLINK {directive}

where *directive* is any of the following:

ALIAS *alias_name=symbol_name{,alias_name=symbol_name}*
DEBUG *dbtype [dblist] /*
DISABLE *msg_num{,msg_num}*
ENDLINK
FILE *obj_spec{,obj_spec}*
FORMAT *DOS [COM]*
LANGUAGE *lang*
LIBFILE *obj_file{,obj_file}*
LIBPATH *path_name{;path_name}*
LIBRARY *library_file{,library_file}*
MODTRACE *obj_module{,obj_module}*
NAME *exe_file*
NEWSEGMENT
OPTION *option{,option}*

ARTIFICIAL
[NO]CACHE
[NO]CASEEXACT
CVPACK
DOSSEG
ELIMINATE
MANGLEDNAMES
MAP[=map_file]

MAXERRORS=*n*
NAMELEN=*n*
NODEFAULTLIBS
OSNAME='string'
PACKCODE=*n*
PACKDATA=*n*
QUIET
REDEFSOK
SHOWDEAD
STACK=*n*
START=*symbol_name*
STATICS
SYMFILE[=*symbol_file*]
[NO]UNDEFSOK
VERBOSE
VFREMOVAL
OPTLIB *library_file*{*library_file*}
PATH *path_name*{;*path_name*}
REFERENCE *symbol_name*{*symbol_name*}
SORT [**GLOBAL**] [**ALPHABETICAL**]
STARTLINK
SYMTRACE *symbol_name*{*symbol_name*}
SYSTEM BEGIN *system_name* {*directive*} **END**
SYSTEM *system_name*
comment
@ directive_file

You can view all the directives specific to DOS executable files by simply typing the following:

```
wlink ? dos
```

Notes:

1. If the file "wlink.hlp" is located in one of the paths specified in the "PATH" environment variable, the contents of that file will be displayed when the following command is issued.

```
wlink ?
```

2. If all of the directive information does not fit on the command line, type the following.

```
wlink
```

The prompt "WLINK>" will appear on the next line. You can enter as many lines of directive information as required. Press "Ctrl/Z" followed by the "Enter" key to terminate the input of directive information if you are running a DOS, OS/2 or Windows NT-hosted version of the Watcom Linker. Press "Ctrl/D" to terminate the input of directive information if you are running a QNX-hosted version of the Watcom Linker.

4.1 Memory Layout

The following describes the segment ordering of an application linked by the Watcom Linker. Note that this assumes that the "DOSSEG" linker option has been specified.

1. all segments not belonging to group "DGROUP" with class "CODE"
2. all other segments not belonging to group "DGROUP"
3. all segments belonging to group "DGROUP" with class "BEGDATA"
4. all segments belonging to group "DGROUP" not with class "BEGDATA", "BSS" or "STACK"
5. all segments belonging to group "DGROUP" with class "BSS"
6. all segments belonging to group "DGROUP" with class "STACK"

A special segment belonging to class "BEGDATA" is defined when linking with Watcom run-time libraries. This segment is initialized with the hexadecimal byte pattern "01" and is the first segment in group "DGROUP" so that storing data at location 0 can be detected.

Segments belonging to class "BSS" contain uninitialized data. Note that this only includes uninitialized data in segments belonging to group "DGROUP". Segments belonging to class "STACK" are used to define the size of the stack used for your application. Segments belonging to the classes "BSS" and "STACK" are last in the segment ordering so that uninitialized data need not take space in the executable file.

4.2 The Watcom Linker Memory Requirements

The Watcom Linker uses all available memory when linking an application. For DOS-hosted versions of the Watcom Linker, this includes expanded memory (EMS) and extended memory. It is possible for the size of the image being linked to exceed the amount of memory available in your machine, particularly if the image file is to contain debugging information. For this reason, a temporary disk file is used when all available memory is used by the Watcom Linker.

Normally, the temporary file is created in the default directory. However, by defining the "tmp" environment variable to be a directory, you can tell the Watcom Linker where to create the temporary file. This can be particularly useful if you have a RAM disk. Consider the following definition of the "tmp" environment variable.

```
set tmp=\tmp
```

The Watcom Linker will create the temporary file in the directory "\tmp".

4.3 Using Overlays

The creation of overlaid executables is not supported by this version of the Watcom Linker.

4.4 Converting Microsoft Response Files to Directive Files

A utility called MS2WLINK can be used to convert Microsoft linker response files to Watcom Linker directive files. The response files must correspond to the linker found in version 7 or earlier of Microsoft C. Later versions of response files such as those used with Microsoft Visual C++ are not entirely supported.

The same utility can also convert much of the content of IBM OS/2 LINK386 response files since the syntax is similar.

Input to MS2WLINK is processed in the same way as the Microsoft linker processes its input. The difference is that MS2WLINK writes the corresponding Watcom Linker directive file to the standard output device instead of creating an executable file. The resulting output can be redirected to a disk file which can then be used as input to the Watcom Linker to produce an executable file.

Suppose you have a Microsoft linker response file called "test.rsp". You can convert this file to a Watcom Linker directive file by issuing the following command.

Example:

```
ms2wlink @test.rsp >test.lnk
```

You can now use the Watcom Linker to link your program by issuing the following command.

Example:

```
wlink @test
```

An alternative way to link your application with the Watcom Linker from a Microsoft response file is to issue the following command.

Example:

```
ms2wlink @test.rsp | wlink
```

Since the Watcom Linker gets its input from the standard input device, you do not have to create a Watcom Linker directive file to link your application.

Note that MS2WLINK can also process module-definition files used for creating OS/2 applications.

5 The ELF Executable File Format

This chapter deals specifically with aspects of ELF executable files. The ELF executable file format will only run under the operating systems that support the ELF executable file format.

Input to the Watcom Linker is specified on the command line and can be redirected to one or more files or environment strings. The Watcom Linker command line format is as follows.

WLINK {directive}

where *directive* is any of the following:

ALIAS *alias_name=symbol_name*{*alias_name=symbol_name*}
DEBUG *dbtype* [*dblist*] |
DISABLE *msg_num*{*msg_num*}
ENDLINK
EXPORT *entry_name* {*entry_name*}
FILE *obj_spec*{*obj_spec*}
FORMAT *ELF* [*DLL*]
IMPORT *external_name* {*external_name*}
LANGUAGE *lang*
LIBFILE *obj_file*{*obj_file*}
LIBPATH *path_name*{*path_name*}
LIBRARY *library_file*{*library_file*}
MODFILE *obj_file*{*obj_file*}
MODTRACE *obj_module*{*obj_module*}
MODULE *module_name* {*module_name*}
NAME *exe_file*
OPTION *option*{*option*}

ALIGNMENT=n
ARTIFICIAL
[NO]CACHE
[NO]CASEEXACT
CVPACK

DOSSEG
ELIMINATE
INCREMENTAL
MANGLEDNAMES
MAP[=*map_file*]
MAXERRORS=*n*
NAMELEN=*n*
NODEFAULTLIBS
OSNAME='string'
QUIET
REDEFSOK
SHOWDEAD
STACK=*n*
START=*symbol_name*
STATICS
SYMFILE[=*symbol_file*]
[NO]UNDEFSOK
VERBOSE
VFREMOVAL
OPTLIB *library_file*{*library_file*}
PATH *path_name*{;*path_name*}
REFERENCE *symbol_name*{*symbol_name*}
SORT [GLOBAL] [ALPHABETICAL]
STARTLINK
SYMTRACE *symbol_name*{*symbol_name*}
SYSTEM BEGIN *system_name* {*directive*} END
SYSTEM *system_name*
*comment*
@ *directive_file*

You can view all the directives specific to ELF executable files by simply typing the following:

```
wlink ? elf
```

Notes:

1. If the file "wlink.hlp" is located in one of the paths specified in the "PATH" environment variable, the contents of that file will be displayed when the following command is issued.

```
wlink ?
```

2. If all of the directive information does not fit on the command line, type the following.

```
wlink
```

The prompt "WLINK>" will appear on the next line. You can enter as many lines of directive information as required. Press "Ctrl/Z" followed by the "Enter" key to terminate the input of directive information if you are running a DOS, OS/2 or Windows NT-hosted version of the Watcom Linker. Press "Ctrl/D" to terminate the input of directive information if you are running a QNX-hosted version of the Watcom Linker.

5.1 Memory Layout

The following describes the segment ordering of an application linked by the Watcom Linker. Note that this assumes that the "DOSSEG" linker option has been specified.

1. all segments not belonging to group "DGROUP" with class "CODE"
2. all other segments not belonging to group "DGROUP"
3. all segments belonging to group "DGROUP" with class "BEGDATA"
4. all segments belonging to group "DGROUP" not with class "BEGDATA", "BSS" or "STACK"
5. all segments belonging to group "DGROUP" with class "BSS"
6. all segments belonging to group "DGROUP" with class "STACK"

A special segment belonging to class "BEGDATA" is defined when linking with Watcom run-time libraries. This segment is initialized with the hexadecimal byte pattern "01" and is the first segment in group "DGROUP" so that storing data at location 0 can be detected.

Segments belonging to class "BSS" contain uninitialized data. Note that this only includes uninitialized data in segments belonging to group "DGROUP". Segments belonging to class "STACK" are used to define the size of the stack used for your application. Segments belonging to the classes "BSS" and "STACK" are last in the segment ordering so that uninitialized data need not take space in the executable file.

5.2 The Watcom Linker Memory Requirements

The Watcom Linker uses all available memory when linking an application. For DOS-hosted versions of the Watcom Linker, this includes expanded memory (EMS) and extended memory. It is possible for the size of the image being linked to exceed the amount of memory available in your machine, particularly if the image file is to contain debugging information. For this reason, a temporary disk file is used when all available memory is used by the Watcom Linker.

Normally, the temporary file is created in the default directory. However, by defining the "tmp" environment variable to be a directory, you can tell the Watcom Linker where to create the temporary file. This can be particularly useful if you have a RAM disk. Consider the following definition of the "tmp" environment variable.

```
set tmp=\tmp
```

The Watcom Linker will create the temporary file in the directory "\tmp".

6 The NetWare 386 Executable File Format

This chapter deals specifically with aspects of NetWare 386 executable files. The Novell NetWare 386 executable file format will only run under the NetWare 386 operating system.

Input to the Watcom Linker is specified on the command line and can be redirected to one or more files or environment strings. The Watcom Linker command line format is as follows.

WLINK {directive}

where *directive* is any of the following:

ALIAS *alias_name*=*symbol_name*{*alias_name*=*symbol_name*}
DEBUG *dbtype* [*dblist*] |
DISABLE *msg_num*{*msg_num*}
ENDLINK
EXPORT *entry_name* {*entry_name*}
FILE *obj_spec*{*obj_spec*}
FORMAT *NOVELL* [*NLM* | *LAN* | *DSK* | *NAM*] '*description*'
IMPORT *external_name* {*external_name*}
LANGUAGE *lang*
LIBFILE *obj_file*{*obj_file*}
LIBPATH *path_name*{*path_name*}
LIBRARY *library_file*{*library_file*}
MODTRACE *obj_module*{*obj_module*}
MODULE *module_name* {*module_name*}
NAME *exe_file*
OPTION *option*{*option*}

ARTIFICIAL
[NO]CACHE
[NO]CASEEXACT
CHECK=*symbol_name*
COPYRIGHT '*string*'
CUSTOM=*file_name*

CVPACK
DOSSEG
ELIMINATE
EXIT=*symbol_name*
HELP=*help_file*
IMPFIL[=*imp_file*]
IMPLIB[=*imp_lib*]
MANGLEDNAMES
MAP=[*map_file*]
MAXERRORS=*n*
MESSAGES=*msg_file*
MULTILOAD
NAMELEN=*n*
NLMFLAGS=*some_value*
NODEFAULTLIBS
OSDOMAIN
OSNAME='*string*'
PSEUDOPREEMPTION
QUIET
REDEFSOK
SHOWDEAD
REENTRANT
SCREENNAME '*name*'
SHARELIB=*shared_nlm*
STACK=*n*
START=*symbol_name*
STATICS
SYMFILE[=*symbol_file*]
SYNCHRONIZE
THREADNAME '*thread_name*'
[NO]UNDEFSOK
VERBOSE
VERSION=*major*[.*minor*][.*revision*]
VFREMOVAL
XDCDATA=*rpc_file*
OPTLIB *library_file*{*library_file*}
PATH *path_name*{;*path_name*}
REFERENCE *symbol_name*{*symbol_name*}
SORT [GLOBAL] [ALPHABETICAL]
STARTLINK
SYMTRACE *symbol_name*{*symbol_name*}
SYSTEM BEGIN *system_name* {*directive*} **END**

SYSTEM *system_name*
comment
@ directive_file

You can view all the directives specific to NetWare 386 executable files by simply typing the following:

```
wlink ? nov
```

Notes:

1. If the file "wlink.hlp" is located in one of the paths specified in the "PATH" environment variable, the contents of that file will be displayed when the following command is issued.

```
wlink ?
```

2. If all of the directive information does not fit on the command line, type the following.

```
wlink
```

The prompt "WLINK>" will appear on the next line. You can enter as many lines of directive information as required. Press "Ctrl/Z" followed by the "Enter" key to terminate the input of directive information if you are running a DOS, OS/2 or Windows NT-hosted version of the Watcom Linker. Press "Ctrl/D" to terminate the input of directive information if you are running a QNX-hosted version of the Watcom Linker.

6.1 NetWare Loadable Modules

NetWare Loadable Modules (NLMs) are executable files that run in file server memory under the NetWare 386 operating system. NLMs can be loaded and unloaded from file server memory while the server is running. When running they actually become part of the operating system thus acting as building blocks for a server environment tailored to your needs.

There are four types of NLMs, each identified by the file extension of the executable file.

- Utility and server applications (executable files with extension "nlm").
- LAN drivers (executable files with extension "lan").

- Disk drivers (executable files with extension "dsk").
- Modules that define file system name spaces (executable files with extension "nam").

The Watcom Linker can generate all four types of NLMs.

6.2 Memory Layout

The following describes the segment ordering of an application linked by the Watcom Linker. Note that this assumes that the "DOSSEG" linker option has been specified.

1. all segments not belonging to group "DGROUP" with class "CODE"
2. all other segments not belonging to group "DGROUP"
3. all segments belonging to group "DGROUP" with class "BEGDATA"
4. all segments belonging to group "DGROUP" not with class "BEGDATA", "BSS" or "STACK"
5. all segments belonging to group "DGROUP" with class "BSS"
6. all segments belonging to group "DGROUP" with class "STACK"

A special segment belonging to class "BEGDATA" is defined when linking with Watcom run-time libraries. This segment is initialized with the hexadecimal byte pattern "01" and is the first segment in group "DGROUP" so that storing data at location 0 can be detected.

Segments belonging to class "BSS" contain uninitialized data. Note that this only includes uninitialized data in segments belonging to group "DGROUP". Segments belonging to class "STACK" are used to define the size of the stack used for your application. Segments belonging to the classes "BSS" and "STACK" are last in the segment ordering so that uninitialized data need not take space in the executable file.

6.3 The Watcom Linker Memory Requirements

The Watcom Linker uses all available memory when linking an application. For DOS-hosted versions of the Watcom Linker, this includes expanded memory (EMS) and extended memory. It is possible for the size of the image being linked to exceed the amount of memory available in your machine, particularly if the image file is to contain debugging information. For this reason, a temporary disk file is used when all available memory is used by the Watcom Linker.

Normally, the temporary file is created in the default directory. However, by defining the "tmp" environment variable to be a directory, you can tell the Watcom Linker where to create the temporary file. This can be particularly useful if you have a RAM disk. Consider the following definition of the "tmp" environment variable.

```
set tmp=\tmp
```

The Watcom Linker will create the temporary file in the directory "\tmp".

7 The OS/2 Executable and DLL File Formats

This chapter deals specifically with aspects of OS/2 executable files. The OS/2 16-bit executable file format will run under the following operating systems.

1. 16-bit OS/2 1.x
2. 32-bit OS/2 2.x and 3.x (Warp)
3. Phar Lap's 286/DOS-Extender

The OS/2 32-bit linear executable file format will run under the following operating systems.

1. OS/2 2.x (LX format only)
2. OS/2 3.x (LX format only)
3. Tenberry Software's DOS/4G and DOS/4GW DOS extenders (LE format only)
4. FlashTek's DOS Extender (LX format only)

Input to the Watcom Linker is specified on the command line and can be redirected to one or more files or environment strings. The Watcom Linker command line format is as follows.

WLINK {directive}

where *directive* is any of the following:

ALIAS *alias_name=symbol_name{,alias_name=symbol_name}*
DEBUG *dbtype [dblist] |*
DISABLE *msg_num{,msg_num}*
ENDLINK
EXPORT *export{,export}*
EXPORT *=lbc_file*
FILE *obj_spec{,obj_spec}*
FORMAT OS2 [*exe_type*] [*dll_form | exe_attrs*]
IMPORT *import{,import}*
LANGUAGE *lang*
LIBFILE *obj_file{,obj_file}*
LIBPATH *path_name{;path_name}*

LIBRARY *library_file*{*library_file*}
MODFILE *obj_file*{*obj_file*}
MODTRACE *obj_module*{*obj_module*}
NAME *exe_file*
NEWSEGMENT
PATH *path_name*{*path_name*}
OPTION *option*{*option*}

ALIGNMENT=*n*
ARTIFICIAL
[NO]CACHE
[NO]CASEEXACT
CVPACK
DESCRIPTION '*string*'
DOSSEG
ELIMINATE
HEAPSIZE=*n*
IMPFILE[=*imp_file*]
IMPLIB[=*imp_lib*]
INCREMENTAL
INTERNALRELOCS
MANGLEDNAMES
MANYAUTODATA
MAP[=*map_file*]
MAXERRORS=*n*
MODNAME=*module_name*
NAMELEN=*n*
NEWFILES
NOAUTODATA
NODEFAULTLIBS
OFFSET
OLDLIBRARY=*dll_name*
ONEAUTODATA
OSNAME='string'
PACKCODE=*n*
PACKDATA=*n*
PROTMODE
QUIET
REDEFSOK
RESOURCE=*resource_file*
SHOWDEAD
STACK=*n*

*START=*symbol_name
STATICS
*STUB=*stub_name
*SYMFILE[=*symbol_file]
TOGGLERELOCS
[NO]UNDEFSOK
VERBOSE
*VERSION=*major[.minor]
VFREMOVAL
OPTLIB library_file{,library_file}
REFERENCE symbol_name{,symbol_name}
SEGMENT seg_desc{,seg_desc}
SORT [GLOBAL] [ALPHABETICAL]
STARTLINK
SYMTRACE symbol_name{,symbol_name}
SYSTEM BEGIN system_name {directive} *END*
SYSTEM system_name
comment
@ directive_file

You can view all the directives specific to OS/2 executable files by simply typing the following:

```
wlink ? os2
```

Notes:

1. If the file "wlink.hlp" is located in one of the paths specified in the "PATH" environment variable, the contents of that file will be displayed when the following command is issued.

```
wlink ?
```

2. If all of the directive information does not fit on the command line, type the following.

```
wlink
```

The prompt "WLINK>" will appear on the next line. You can enter as many lines of directive information as required. Press "Ctrl/Z" followed by the "Enter" key to terminate the input of directive information if you are running a DOS, OS/2 or Windows NT-hosted version of the Watcom Linker. Press "Ctrl/D" to terminate the input of directive information if you are running a QNX-hosted version of the Watcom Linker.

7.1 Dynamic Link Libraries

The Watcom Linker can generate two forms of executable files; program modules and Dynamic Link Libraries. A program module is the executable file that gets loaded by the operating system when you run your application. A Dynamic Link Library is really a library of routines that are called by a program module but not linked into the program module. The executable code in a Dynamic Link Library is loaded by the operating system during the execution of a program module when a routine in the Dynamic Link Library is called.

Program modules are contained in files whose name has a file extension of ".exe". Dynamic Link Libraries are contained in files whose name has a file extension of ".dll". The Watcom Linker "FORMAT" directive can be used to select the type of executable file to be generated.

Let us consider some of the advantages of using Dynamic Link Libraries over standard libraries.

1. Functions in Dynamic Link Libraries are not linked into your program. Only references to the functions in Dynamic Link Libraries are placed in the program module. These references are called import definitions. As a result, the linking time is reduced and disk space is saved. If many applications reference the same Dynamic Link Library, the saving in disk space can be significant.
2. Since program modules only reference Dynamic Link Libraries and do not contain the actual executable code, a Dynamic Link Library can be updated without re-linking your application. When your application is executed, it will use the updated version of the Dynamic Link Library.
3. Dynamic Link Libraries also allow sharing of code and data between the applications that use them. If many applications that use the same Dynamic Link Library are executing concurrently, the sharing of code and data segments improves memory utilization.

7.1.1 Creating a Dynamic Link Library

To create a Dynamic Link Library, you must place the "DLL" keyword following the system name in the "SYSTEM" directive.

```
system system os2v2 dll
```

In addition, you must specify which functions in the Dynamic Link Library are to be made available to applications which use it. This is achieved by using the "EXPORT" directive for each function that can be called by an application.

Dynamic Link Libraries can reference other Dynamic Link Libraries. References to other Dynamic Link Libraries are resolved by specifying "IMPORT" directives or using import libraries.

7.1.2 Using a Dynamic Link Library

To use a Dynamic Link Library, you must tell the Watcom Linker which functions are contained in a Dynamic Link Library and the name of the Dynamic Link Library. This is achieved in two ways.

The first method is to use the "IMPORT" directive. The "IMPORT" directive names the function and the Dynamic Link Library it belongs to so that the Watcom Linker can generate an import definition in the program module.

The second method is to use import libraries. An import library is a standard library which contains object modules with special object records that define the functions belonging to a Dynamic Link Library. An import library is created from a Dynamic Link Library using the Watcom Library Manager. The resulting import library can then be specified in a "LIBRARY" directive in the same way one would specify a standard library. See the chapter entitled "The Watcom Library Manager" in the *Watcom C/C++ Tools User's Guide* or the *Watcom FORTRAN 77 Tools User's Guide* for more information on creating import libraries.

Using an import library is the preferred method of providing references to functions in Dynamic Link Libraries. When a Dynamic Link Library is modified, typically the import library corresponding to the modified Dynamic Link Library is updated to reflect the changes. Hence, any directive file that specifies the import library in a "LIBRARY" directive need not be modified. However, if you are using "IMPORT" directives, you may have to modify the "IMPORT" directives to reflect the changes in the Dynamic Link Library.

7.2 Memory Layout

The following describes the segment ordering of an application linked by the Watcom Linker. Note that this assumes that the "DOSSEG" linker option has been specified.

1. all segments not belonging to group "DGROUP" with class "CODE"
2. all other segments not belonging to group "DGROUP"
3. all segments belonging to group "DGROUP" with class "BEGDATA"

4. all segments belonging to group "DGROUP" not with class "BEGDATA", "BSS" or "STACK"
5. all segments belonging to group "DGROUP" with class "BSS"
6. all segments belonging to group "DGROUP" with class "STACK"

A special segment belonging to class "BEGDATA" is defined when linking with Watcom run-time libraries. This segment is initialized with the hexadecimal byte pattern "01" and is the first segment in group "DGROUP" so that storing data at location 0 can be detected.

Segments belonging to class "BSS" contain uninitialized data. Note that this only includes uninitialized data in segments belonging to group "DGROUP". Segments belonging to class "STACK" are used to define the size of the stack used for your application. Segments belonging to the classes "BSS" and "STACK" are last in the segment ordering so that uninitialized data need not take space in the executable file.

7.3 The Watcom Linker Memory Requirements

The Watcom Linker uses all available memory when linking an application. For DOS-hosted versions of the Watcom Linker, this includes expanded memory (EMS) and extended memory. It is possible for the size of the image being linked to exceed the amount of memory available in your machine, particularly if the image file is to contain debugging information. For this reason, a temporary disk file is used when all available memory is used by the Watcom Linker.

Normally, the temporary file is created in the default directory. However, by defining the "tmp" environment variable to be a directory, you can tell the Watcom Linker where to create the temporary file. This can be particularly useful if you have a RAM disk. Consider the following definition of the "tmp" environment variable.

```
set tmp=\tmp
```

The Watcom Linker will create the temporary file in the directory "\\tmp".

7.4 Converting Microsoft Response Files to Directive Files

A utility called MS2WLINK can be used to convert Microsoft linker response files to Watcom Linker directive files. The response files must correspond to the linker found in version 7 or earlier of Microsoft C. Later versions of response files such as those used with Microsoft Visual C++ are not entirely supported.

The same utility can also convert much of the content of IBM OS/2 LINK386 response files since the syntax is similar.

Input to MS2WLINK is processed in the same way as the Microsoft linker processes its input. The difference is that MS2WLINK writes the corresponding Watcom Linker directive file to the standard output device instead of creating an executable file. The resulting output can be redirected to a disk file which can then be used as input to the Watcom Linker to produce an executable file.

Suppose you have a Microsoft linker response file called "test.rsp". You can convert this file to a Watcom Linker directive file by issuing the following command.

Example:

```
ms2wlink @test.rsp >test.lnk
```

You can now use the Watcom Linker to link your program by issuing the following command.

Example:

```
wlink @test
```

An alternative way to link your application with the Watcom Linker from a Microsoft response file is to issue the following command.

Example:

```
ms2wlink @test.rsp | wlink
```

Since the Watcom Linker gets its input from the standard input device, you do not have to create a Watcom Linker directive file to link your application.

Note that MS2WLINK can also process module-definition files used for creating OS/2 applications.

8 The Phar Lap Executable File Format

This chapter deals specifically with aspects of Phar Lap 386|DOS-Extender executable files. The Phar Lap executable file format will run under the following operating systems.

1. Phar Lap's 386|DOS-Extender
2. Watcom's 32-bit Windows supervisor (relocatable format only)

Input to the Watcom Linker is specified on the command line and can be redirected to one or more files or environment strings. The Watcom Linker command line format is as follows.

WLINK {directive}

where *directive* is any of the following:

ALIAS *alias_name=symbol_name*{*alias_name=symbol_name*}
DEBUG *dbtype* [*dblist*] |
DISABLE *msg_num*{*msg_num*}
ENDLINK
FILE *obj_spec*{*obj_spec*}
FORMAT *PHARLAP* [*EXTENDED* | *REX* | *SEGMENTED*]
LANGUAGE *lang*
LIBFILE *obj_file*{*obj_file*}
LIBPATH *path_name*{*path_name*}
LIBRARY *library_file*{*library_file*}
MODFILE *obj_file*{*obj_file*}
MODTRACE *obj_module*{*obj_module*}
NAME *exe_file*
OPTION *option*{*option*}

ARTIFICIAL
[NO]CACHE
[NO]CASEEXACT
CVPACK
DOSSEG

ELIMINATE
INCREMENTAL
MANGLEDNAMES
MAP[=map_file]
MAXDATA=n
MAXERRORS=n
MINDATA=n
NAMELEN=n
NODEFAULTLIBS
OFFSET=n
OSNAME='string'
QUIET
REDEFSOK
SHOWDEAD
STACK=n
START=symbol_name
STATICS
SYMFILE[=symbol_file]
[NO]UNDEFSOK
VERBOSE
VFREMOVAL
OPTLIB library_file{,library_file}
PATH path_name{;path_name}
REFERENCE symbol_name{,symbol_name}
RUNTIME run_option{,run_option}
SORT [GLOBAL] [ALPHABETICAL]
STARTLINK
SYMTRACE symbol_name{,symbol_name}
SYSTEM BEGIN system_name {directive} END
SYSTEM system_name
comment
@ directive_file

You can view all the directives specific to Phar Lap 386|DOS-Extender executable files by simply typing the following:

```
wlink ? phar
```

Notes:

1. If the file "wlink.hlp" is located in one of the paths specified in the "PATH" environment variable, the contents of that file will be displayed when the following command is issued.

wlink ?

2. If all of the directive information does not fit on the command line, type the following.

wlink

The prompt "WLINK>" will appear on the next line. You can enter as many lines of directive information as required. Press "Ctrl/Z" followed by the "Enter" key to terminate the input of directive information if you are running a DOS, OS/2 or Windows NT-hosted version of the Watcom Linker. Press "Ctrl/D" to terminate the input of directive information if you are running a QNX-hosted version of the Watcom Linker.

8.1 32-bit Protected-Mode Applications

The Watcom Linker generates executable files that run under Phar Lap's 386|DOS-Extender. 386|DOS-Extender provides a 32-bit protected-mode environment for programs running under PC DOS. Running in 32-bit protected mode allows your program to access all of the memory in your machine.

Essentially, what 386|DOS-Extender does is provide an interface between your application and DOS running in real mode. Whenever your program issues a software interrupt (DOS and BIOS system calls), 386|DOS-Extender intercepts the requests, transfers data between the protected-mode and real-mode address space, and calls the corresponding DOS system function running in real mode.

8.2 Memory Usage

When running a program under 386|DOS-Extender, memory for the program is allocated from conventional memory (memory below one megabyte) and extended memory. Conventional memory is allocated from a block of memory that is obtained from DOS by 386|DOS-Extender at initialization time. By default, all available memory is allocated at initialization time; no conventional memory remains free. The "MINREAL" and "MAXREAL" options of the "RUNTIME" directive control the amount of conventional memory initially left free by 386|DOS-Extender.

Part of the conventional memory allocated at initialization is required by 386|DOS-Extender. The following is allocated from conventional memory for use by 386|DOS-Extender.

1. A data buffer is allocated and is used to pass data to DOS and BIOS system functions. The size allocated is controlled by the "MINIBUF" and "MAXIBUF" options of the "RUNTIME" directive.
2. Stack space is allocated and is used for switching between 32-bit protected mode and real mode. The size allocated is controlled by the "NISTACK" and "ISTKSIZE" options of the "RUNTIME" directive.
3. A call buffer is allocated and is used for passing data on function calls between 32-bit protected mode and real mode. The size allocated is controlled by the "CALLBUFS" option of the "RUNTIME" directive.

When a program is loaded by 386DOS-Extender, memory to hold the entire program is allocated. In addition, memory beyond the end of the program is allocated for use by the program. By default, all extra memory is allocated when the program is loaded. It is assumed that any memory not required by the program is freed by the program. The amount of memory allocated at the end of the program is controlled by the "MINDATA" and "MAXDATA" options.

8.3 Memory Layout

The following describes the segment ordering of an application linked by the Watcom Linker. Note that this assumes that the "DOSSEG" linker option has been specified.

1. all "USE16" segments. These segments are present in applications that execute in both real mode and protected mode. They are first in the segment ordering so that the "REALBREAK" option of the "RUNTIME" directive can be used to separate the real-mode part of the application from the protected-mode part of the application. Currently, the "RUNTIME" directive is valid for Phar Lap executables only.
2. all segments not belonging to group "DGROUP" with class "CODE"
3. all other segments not belonging to group "DGROUP"
4. all segments belonging to group "DGROUP" with class "BEGDATA"
5. all segments belonging to group "DGROUP" not with class "BEGDATA", "BSS" or "STACK"
6. all segments belonging to group "DGROUP" with class "BSS"

192 Memory Layout

7. all segments belonging to group "DGROUP" with class "STACK"

Segments belonging to class "BSS" contain uninitialized data. Note that this only includes uninitialized data in segments belonging to group "DGROUP". Segments belonging to class "STACK" are used to define the size of the stack used for your application. Segments belonging to the classes "BSS" and "STACK" are last in the segment ordering so that uninitialized data need not take space in the executable file.

8.4 The Watcom Linker Memory Requirements

The Watcom Linker uses all available memory when linking an application. For DOS-hosted versions of the Watcom Linker, this includes expanded memory (EMS) and extended memory. It is possible for the size of the image being linked to exceed the amount of memory available in your machine, particularly if the image file is to contain debugging information. For this reason, a temporary disk file is used when all available memory is used by the Watcom Linker.

Normally, the temporary file is created in the default directory. However, by defining the "tmp" environment variable to be a directory, you can tell the Watcom Linker where to create the temporary file. This can be particularly useful if you have a RAM disk. Consider the following definition of the "tmp" environment variable.

```
set tmp=\tmp
```

The Watcom Linker will create the temporary file in the directory "\\tmp".

9 The QNX Executable File Format

This chapter deals specifically with aspects of QNX executable files. The QNX executable file format will only run under the QNX operating system.

Input to the Watcom Linker is specified on the command line and can be redirected to one or more files or environment strings. The Watcom Linker command line format is as follows.

wlink {directive}

where *directive* is any of the following:

ALIAS symbol_name=symbol_name{,symbol_name=symbol_name}
DEBUG dbtype [dblist] /
DISABLE msg_num{,msg_num}
ENDLINK
FILE obj_spec{,obj_spec}
FORMAT QNX [FLAT]
LANGUAGE
LIBFILE obj_file{,obj_file}
LIBPATH path_name{:path_name}
LIBRARY library_file{,library_file}
MODFILE obj_file{,obj_file}
MODTRACE obj_spec{,obj_spec}
NAME exe_file
NEWSEGMENT
OPTION option{,option}

ARTIFICIAL
[NO]CACHE
[NO]CASEEXACT
CVPACK
DOSSEG
ELIMINATE
HEAPSIZE=n

INCREMENTAL
LINEARRELOCS
LOGLIVED
MANGLEDNAMES
MAP[=map_file]
MAXERRORS=n
NAMELEN=n
NODEFAULTLIBS
NORELOCS
OFFSET=n
OSNAME='string'
PACKCODE=n
PACKDATA=n
PRIVILEGE=n
QUIET
REDEFSOK
RESOURCE[=resource_file / 'string']
SHOWDEAD
STACK=n
START=symbol_name
STATICS
SYMFILE[=symbol_file]
[NO]UNDEFSOK
VERBOSE
VFREMOVAL
OPTLIB library_file{,library_file}
PATH path_name{:path_name}
REFERENCE symbol_name{,symbol_name}
SEGMENT seg_desc{,seg_desc}
SORT [GLOBAL] [ALPHABETICAL]
STARTLINK
SYMTRACE symbol_name{,symbol_name}
SYSTEM BEGIN system_name {directive} END
SYSTEM system_name
comment
@ directive_file

You can view all the directives specific to QNX executable files by simply typing the following:

```
wlink ? qnx
```

Notes:

1. If the file `/etc/wlink.hlp` exists, the contents of that file will be displayed when the following command is issued.

```
wlink ?
```

2. If all of the directive information does not fit on the command line, type the following.

```
wlink
```

The prompt "WLINK>" will appear on the next line. You can enter as many lines of directive information as required. Press "Ctrl/Z" followed by the "Enter" key to terminate the input of directive information if you are running a DOS, OS/2 or Windows NT-hosted version of the Watcom Linker. Press "Ctrl/D" to terminate the input of directive information if you are running a QNX-hosted version of the Watcom Linker.

9.1 Memory Layout

The following describes the segment ordering of an application linked by the Watcom Linker. Note that this assumes that the "DOSSEG" linker option has been specified.

1. all segments not belonging to group "DGROUP" with class "CODE"
2. all other segments not belonging to group "DGROUP"
3. all segments belonging to group "DGROUP" with class "BEGDATA"
4. all segments belonging to group "DGROUP" not with class "BEGDATA", "BSS" or "STACK"
5. all segments belonging to group "DGROUP" with class "BSS"
6. all segments belonging to group "DGROUP" with class "STACK"

A special segment belonging to class "BEGDATA" is defined when linking with Watcom run-time libraries. This segment is initialized with the hexadecimal byte pattern "01" and is the first segment in group "DGROUP" so that storing data at location 0 can be detected.

Segments belonging to class "BSS" contain uninitialized data. Note that this only includes uninitialized data in segments belonging to group "DGROU". Segments belonging to class "STACK" are used to define the size of the stack used for your application. Segments belonging to the classes "BSS" and "STACK" are last in the segment ordering so that uninitialized data need not take space in the executable file.

9.2 The Watcom Linker Memory Requirements

The Watcom Linker uses all available memory when linking an application. For DOS-hosted versions of the Watcom Linker, this includes expanded memory (EMS) and extended memory. It is possible for the size of the image being linked to exceed the amount of memory available in your machine, particularly if the image file is to contain debugging information. For this reason, a temporary disk file is used when all available memory is used by the Watcom Linker.

Normally, the temporary file is created in the current working directory. However, by defining the "TMPDIR" environment variable to be a directory, you can tell the Watcom Linker where to create the temporary file. This can be particularly useful if you have a RAM disk. Consider the following definition of the "TMPDIR" environment variable.

```
export TMPDIR=/tmp
```

The Watcom Linker will create the temporary file in the directory "/tmp".

10 The Win16 Executable and DLL File Formats

This chapter deals specifically with aspects of Win16 executable files. The Win16 executable file format will run under Windows 3.x, Windows 95, and Windows NT.

Input to the Watcom Linker is specified on the command line and can be redirected to one or more files or environment strings. The Watcom Linker command line format is as follows.

WLINK {directive}

where *directive* is any of the following:

ALIAS *alias_name*=*symbol_name*{*alias_name*=*symbol_name*}

ANONYMOUSEXPORT *export*{*export*} | =*lbc_file*

DEBUG *dbtype* [*dblist*] |

DISABLE *msg_num*{*msg_num*}

ENDLINK

EXPORT *export*{*export*}

EXPORT =*lbc_file*

FILE *obj_spec*{*obj_spec*}

FORMAT *WINDOWS* [*dll_form*] [*MEMORY*] [*FONT*]

IMPORT *import*{*import*}

LANGUAGE *lang*

LIBFILE *obj_file*{*obj_file*}

LIBPATH *path_name*{;*path_name*}

LIBRARY *library_file*{*library_file*}

MODFILE *obj_file*{*obj_file*}

MODTRACE *obj_module*{*obj_module*}

NAME *exe_file*

NEWSEGMENT

PATH *path_name*{;*path_name*}

OPTION *option*{*option*}

ALIGNMENT=*n*
ARTIFICIAL
[NO]CACHE
[NO]CASEEXACT
CVPACK
DESCRIPTION 'string'
DOSSEG
ELIMINATE
HEAPSIZE=*n*
IMPFIL[=*imp_file*]
IMPLIB[=*imp_lib*]
INCREMENTAL
MANGLEDNAMES
MANYAUTODATA
MAP[=*map_file*]
MAXERRORS=*n*
MODNAME=*module_name*
NAMELEN=*n*
NOAUTODATA
NODEFAULTLIBS
OLDLIBRARY=*dll_name*
ONEAUTODATA
OSNAME='string'
PACKCODE=*n*
PACKDATA=*n*
QUIET
REDEFSOK
RESOURCE=*resource_file*
RWRELOCHECK
SHOWDEAD
STACK=*n*
START=*symbol_name*
STATICS
STUB=*stub_name*
SYMFILE[=*symbol_file*]
[NO]UNDEFSOK
VERBOSE
VERSION=*major*[.*minor*]
VFREMOVAL
OPTLIB *library_file*{*library_file*}
REFERENCE *symbol_name*{*symbol_name*}
SEGMENT *seg_desc*{*seg_desc*}

SORT [GLOBAL] [ALPHABETICAL]
STARTLINK
***SYMTRACE** symbol_name{,symbol_name}*
SYSTEM BEGIN** system_name {directive} **END
***SYSTEM** system_name*
comment
@ directive_file

You can view all the directives specific to Win16 executable files by simply typing the following:

```
wlink ? win
```

Notes:

1. If the file "wlink.hlp" is located in one of the paths specified in the "PATH" environment variable, the contents of that file will be displayed when the following command is issued.

```
wlink ?
```

2. If all of the directive information does not fit on the command line, type the following.

```
wlink
```

The prompt "WLINK>" will appear on the next line. You can enter as many lines of directive information as required. Press "Ctrl/Z" followed by the "Enter" key to terminate the input of directive information if you are running a DOS, OS/2 or Windows NT-hosted version of the Watcom Linker. Press "Ctrl/D" to terminate the input of directive information if you are running a QNX-hosted version of the Watcom Linker.

10.1 Fixed and Moveable Segments

All segments have attributes that tell Windows how to manage the segment. One of these attributes specifies whether the segment is fixed or moveable. Moveable segments can be moved in memory to satisfy other memory requests. When a segment is moved, all near pointers to that segment are still valid since a near pointer references memory relative to the start of the segment. However, far pointers are no longer valid once a segment has been moved. Fixed segments, on the other hand, cannot be moved in memory. A segment must be fixed if there exists far pointers to that segment that Windows cannot adjust if that segment were moved.

This is a memory-management issue for real-mode Windows only. However, if a DLL is marked as "fixed", Windows 3.x will place it in the lower 640K real-mode memory (regardless of the mode in which Windows 3.x is running). Since the lower 640K is a limited resource, you normally would want a DLL to be marked as "moveable".

Most segments, including code and data segments, are moveable. Some exceptions exist. If your program contains a far pointer, the segment which it references must be fixed. If it were moveable, the segment address portion of the far pointer would be invalid when Windows moved the segment.

All non-Windows programs are assigned fixed segments when they run under Windows. These segments must be fixed since there is no information in the executable file that describes how segments are referenced. Whenever possible, your application should consist of moveable segments since fixed segments can cause memory management problems.

10.2 Discardable Segments

Moveable segments can also be discardable. Memory allocated to a discardable segment can be freed and used for other memory requests. A "least recently used" (LRU) algorithm is used to determine which segment to discard when more memory is required.

Discardable segments are usually segments that do not change once they are loaded into memory. For example, code segments are discardable since programs do not usually modify their code segments. When a segment is discarded, it can be reloaded into memory by accessing the executable file.

Discardable segments must be moveable since they can be reloaded into a different area in memory than the area they previously occupied. Note that moveable segments need not be discardable. Obviously, data segments that contain read/write data cannot be discarded.

10.3 Dynamic Link Libraries

The Watcom Linker can generate two forms of executable files; program modules and Dynamic Link Libraries. A program module is the executable file that gets loaded by the operating system when you run your application. A Dynamic Link Library is really a library of routines that are called by a program module but not linked into the program module. The executable code in a Dynamic Link Library is loaded by the operating system during the execution of a program module when a routine in the Dynamic Link Library is called.

Program modules are contained in files whose name has a file extension of ".exe". Dynamic Link Libraries are contained in files whose name has a file extension of ".dll". The Watcom Linker "FORMAT" directive can be used to select the type of executable file to be generated.

Let us consider some of the advantages of using Dynamic Link Libraries over standard libraries.

1. Functions in Dynamic Link Libraries are not linked into your program. Only references to the functions in Dynamic Link Libraries are placed in the program module. These references are called import definitions. As a result, the linking time is reduced and disk space is saved. If many applications reference the same Dynamic Link Library, the saving in disk space can be significant.
2. Since program modules only reference Dynamic Link Libraries and do not contain the actual executable code, a Dynamic Link Library can be updated without re-linking your application. When your application is executed, it will use the updated version of the Dynamic Link Library.
3. Dynamic Link Libraries also allow sharing of code and data between the applications that use them. If many applications that use the same Dynamic Link Library are executing concurrently, the sharing of code and data segments improves memory utilization.

10.3.1 Creating a Dynamic Link Library

To create a Dynamic Link Library, you must place the "DLL" keyword following the system name in the "SYSTEM" directive.

```
system system windows_dll
```

In addition, you must specify which functions in the Dynamic Link Library are to be made available to applications which use it. This is achieved by using the "EXPORT" directive for each function that can be called by an application.

Dynamic Link Libraries can reference other Dynamic Link Libraries. References to other Dynamic Link Libraries are resolved by specifying "IMPORT" directives or using import libraries.

10.3.2 Using a Dynamic Link Library

To use a Dynamic Link Library, you must tell the Watcom Linker which functions are contained in a Dynamic Link Library and the name of the Dynamic Link Library. This is achieved in two ways.

The first method is to use the "IMPORT" directive. The "IMPORT" directive names the function and the Dynamic Link Library it belongs to so that the Watcom Linker can generate an import definition in the program module.

The second method is to use import libraries. An import library is a standard library which contains object modules with special object records that define the functions belonging to a Dynamic Link Library. An import library is created from a Dynamic Link Library using the Watcom Library Manager. The resulting import library can then be specified in a "LIBRARY" directive in the same way one would specify a standard library. See the chapter entitled "The Watcom Library Manager" in the *Watcom C/C++ Tools User's Guide* or the *Watcom FORTRAN 77 Tools User's Guide* for more information on creating import libraries.

Using an import library is the preferred method of providing references to functions in Dynamic Link Libraries. When a Dynamic Link Library is modified, typically the import library corresponding to the modified Dynamic Link Library is updated to reflect the changes. Hence, any directive file that specifies the import library in a "LIBRARY" directive need not be modified. However, if you are using "IMPORT" directives, you may have to modify the "IMPORT" directives to reflect the changes in the Dynamic Link Library.

10.4 Memory Layout

The following describes the segment ordering of an application linked by the Watcom Linker. Note that this assumes that the "DOSSEG" linker option has been specified.

1. all segments not belonging to group "DGROUP" with class "CODE"
2. all other segments not belonging to group "DGROUP"
3. all segments belonging to group "DGROUP" with class "BEGDATA"
4. all segments belonging to group "DGROUP" not with class "BEGDATA", "BSS" or "STACK"
5. all segments belonging to group "DGROUP" with class "BSS"

6. all segments belonging to group "DGROUP" with class "STACK"

A special segment belonging to class "BEGDATA" is defined when linking with Watcom run-time libraries. This segment is initialized with the hexadecimal byte pattern "01" and is the first segment in group "DGROUP" so that storing data at location 0 can be detected.

Segments belonging to class "BSS" contain uninitialized data. Note that this only includes uninitialized data in segments belonging to group "DGROUP". Segments belonging to class "STACK" are used to define the size of the stack used for your application. Segments belonging to the classes "BSS" and "STACK" are last in the segment ordering so that uninitialized data need not take space in the executable file.

10.5 The Watcom Linker Memory Requirements

The Watcom Linker uses all available memory when linking an application. For DOS-hosted versions of the Watcom Linker, this includes expanded memory (EMS) and extended memory. It is possible for the size of the image being linked to exceed the amount of memory available in your machine, particularly if the image file is to contain debugging information. For this reason, a temporary disk file is used when all available memory is used by the Watcom Linker.

Normally, the temporary file is created in the default directory. However, by defining the "tmp" environment variable to be a directory, you can tell the Watcom Linker where to create the temporary file. This can be particularly useful if you have a RAM disk. Consider the following definition of the "tmp" environment variable.

```
set tmp=\tmp
```

The Watcom Linker will create the temporary file in the directory "\tmp".

10.6 Converting Microsoft Response Files to Directive Files

A utility called MS2WLINK can be used to convert Microsoft linker response files to Watcom Linker directive files. The response files must correspond to the linker found in version 7 or earlier of Microsoft C. Later versions of response files such as those used with Microsoft Visual C++ are not entirely supported.

The same utility can also convert much of the content of IBM OS/2 LINK386 response files since the syntax is similar.

Input to MS2WLINK is processed in the same way as the Microsoft linker processes its input. The difference is that MS2WLINK writes the corresponding Watcom Linker directive file to the standard output device instead of creating an executable file. The resulting output can be redirected to a disk file which can then be used as input to the Watcom Linker to produce an executable file.

Suppose you have a Microsoft linker response file called "test.rsp". You can convert this file to a Watcom Linker directive file by issuing the following command.

Example:

```
ms2wlink @test.rsp >test.lnk
```

You can now use the Watcom Linker to link your program by issuing the following command.

Example:

```
wlink @test
```

An alternative way to link your application with the Watcom Linker from a Microsoft response file is to issue the following command.

Example:

```
ms2wlink @test.rsp | wlink
```

Since the Watcom Linker gets its input from the standard input device, you do not have to create a Watcom Linker directive file to link your application.

Note that MS2WLINK can also process module-definition files used for creating OS/2 applications.

11 The Win32 Executable and DLL File Formats

This chapter deals specifically with aspects of Win32 executable files. The Win32 executable file format will run under Windows 95, Windows NT, and Phar Lap's TNT DOS extender. It may also run under Windows 3.x using the Win32S subsystem (you are restricted to a subset of the Win32 API).

Input to the Watcom Linker is specified on the command line and can be redirected to one or more files or environment strings. The Watcom Linker command line format is as follows.

WLINK {directive}

where *directive* is any of the following:

ALIAS alias_name=symbol_name{,alias_name=symbol_name}
ANONYMOUSEXPORT export{,export} | =lbc_file
COMMIT mem_type
DEBUG dbtype [dblist] |
DISABLE msg_num{,msg_num}
ENDLINK
EXPORT export{,export}
EXPORT =lbc_file
FILE obj_spec{,obj_spec}
FORMAT WINDOWS NT [TNT] [dll_form]
IMPORT import{,import}
LANGUAGE lang
LIBFILE obj_file{,obj_file}
LIBPATH path_name{;path_name}
LIBRARY library_file{,library_file}
MODFILE obj_file{,obj_file}
MODTRACE obj_module{,obj_module}
NAME exe_file

PATH *path_name*{;*path_name*}

OPTION *option*{*option*}

ALIGNMENT=*n*

ARTIFICIAL

[NO]CACHE

[NO]CASEEXACT

CVPACK

DESCRIPTION '*string*'

DOSSEG

ELIMINATE

HEAPSIZE=*n*

IMPFIL[=*imp_file*]

IMPLIB[=*imp_lib*]

INCREMENTAL

MANGLEDNAMES

MAP[=*map_file*]

MAXERRORS=*n*

MODNAME=*module_name*

NAMELEN=*n*

NODEFAULTLIBS

NORELOCS

NOSTDCALL

OBJALIGN=*n*

OFFSET

OLDLIBRARY=*dll_name*

OSNAME='string'

QUIET

REDEFSOK

RESOURCE=*resource_file*

SHOWDEAD

STACK=*n*

START=*symbol_name*

STATICS

STUB=*stub_name*

SYMFILE[=*symbol_file*]

[NO]UNDEFSOK

VERBOSE

VERSION=*major*[.*minor*]

VFREMOVAL

OPTLIB *library_file*{*library_file*}

REFERENCE *symbol_name*{*symbol_name*}

RUNTIME *run_option*
SEGMENT *seg_desc*{*seg_desc*}
SORT [*GLOBAL*] [*ALPHABETICAL*]
STARTLINK
SYMTRACE *symbol_name*{*symbol_name*}
SYSTEM BEGIN *system_name* {*directive*} *END*
SYSTEM *system_name*
comment
@ directive_file

You can view all the directives specific to Win32 executable files by simply typing the following:

```
wlink ? nt
```

Notes:

1. If the file "wlink.hlp" is located in one of the paths specified in the "PATH" environment variable, the contents of that file will be displayed when the following command is issued.

```
wlink ?
```

2. If all of the directive information does not fit on the command line, type the following.

```
wlink
```

The prompt "WLINK>" will appear on the next line. You can enter as many lines of directive information as required. Press "Ctrl/Z" followed by the "Enter" key to terminate the input of directive information if you are running a DOS, OS/2 or Windows NT-hosted version of the Watcom Linker. Press "Ctrl/D" to terminate the input of directive information if you are running a QNX-hosted version of the Watcom Linker.

11.1 Dynamic Link Libraries

The Watcom Linker can generate two forms of executable files; program modules and Dynamic Link Libraries. A program module is the executable file that gets loaded by the operating system when you run your application. A Dynamic Link Library is really a library of routines that are called by a program module but not linked into the program module. The executable code in a Dynamic Link Library is loaded by the operating system during the execution of a program module when a routine in the Dynamic Link Library is called.

Program modules are contained in files whose name has a file extension of ".exe". Dynamic Link Libraries are contained in files whose name has a file extension of ".dll". The Watcom Linker "FORMAT" directive can be used to select the type of executable file to be generated.

Let us consider some of the advantages of using Dynamic Link Libraries over standard libraries.

1. Functions in Dynamic Link Libraries are not linked into your program. Only references to the functions in Dynamic Link Libraries are placed in the program module. These references are called import definitions. As a result, the linking time is reduced and disk space is saved. If many applications reference the same Dynamic Link Library, the saving in disk space can be significant.
2. Since program modules only reference Dynamic Link Libraries and do not contain the actual executable code, a Dynamic Link Library can be updated without re-linking your application. When your application is executed, it will use the updated version of the Dynamic Link Library.
3. Dynamic Link Libraries also allow sharing of code and data between the applications that use them. If many applications that use the same Dynamic Link Library are executing concurrently, the sharing of code and data segments improves memory utilization.

11.1.1 Creating a Dynamic Link Library

To create a Dynamic Link Library, you must place the "DLL" keyword following the system name in the "SYSTEM" directive.

```
system system nt_win dll
```

In addition, you must specify which functions in the Dynamic Link Library are to be made available to applications which use it. This is achieved by using the "EXPORT" directive for each function that can be called by an application.

Dynamic Link Libraries can reference other Dynamic Link Libraries. References to other Dynamic Link Libraries are resolved by specifying "IMPORT" directives or using import libraries.

11.1.2 Using a Dynamic Link Library

To use a Dynamic Link Library, you must tell the Watcom Linker which functions are contained in a Dynamic Link Library and the name of the Dynamic Link Library. This is achieved in two ways.

The first method is to use the "IMPORT" directive. The "IMPORT" directive names the function and the Dynamic Link Library it belongs to so that the Watcom Linker can generate an import definition in the program module.

The second method is to use import libraries. An import library is a standard library which contains object modules with special object records that define the functions belonging to a Dynamic Link Library. An import library is created from a Dynamic Link Library using the Watcom Library Manager. The resulting import library can then be specified in a "LIBRARY" directive in the same way one would specify a standard library. See the chapter entitled "The Watcom Library Manager" in the *Watcom C/C++ Tools User's Guide* or the *Watcom FORTRAN 77 Tools User's Guide* for more information on creating import libraries.

Using an import library is the preferred method of providing references to functions in Dynamic Link Libraries. When a Dynamic Link Library is modified, typically the import library corresponding to the modified Dynamic Link Library is updated to reflect the changes. Hence, any directive file that specifies the import library in a "LIBRARY" directive need not be modified. However, if you are using "IMPORT" directives, you may have to modify the "IMPORT" directives to reflect the changes in the Dynamic Link Library.

11.2 Memory Layout

The following describes the segment ordering of an application linked by the Watcom Linker. Note that this assumes that the "DOSSEG" linker option has been specified.

1. all segments not belonging to group "DGROUP" with class "CODE"
2. all other segments not belonging to group "DGROUP"
3. all segments belonging to group "DGROUP" with class "BEGDATA"
4. all segments belonging to group "DGROUP" not with class "BEGDATA", "BSS" or "STACK"
5. all segments belonging to group "DGROUP" with class "BSS"

6. all segments belonging to group "DGROUP" with class "STACK"

A special segment belonging to class "BEGDATA" is defined when linking with Watcom run-time libraries. This segment is initialized with the hexadecimal byte pattern "01" and is the first segment in group "DGROUP" so that storing data at location 0 can be detected.

Segments belonging to class "BSS" contain uninitialized data. Note that this only includes uninitialized data in segments belonging to group "DGROUP". Segments belonging to class "STACK" are used to define the size of the stack used for your application. Segments belonging to the classes "BSS" and "STACK" are last in the segment ordering so that uninitialized data need not take space in the executable file.

11.3 The Watcom Linker Memory Requirements

The Watcom Linker uses all available memory when linking an application. For DOS-hosted versions of the Watcom Linker, this includes expanded memory (EMS) and extended memory. It is possible for the size of the image being linked to exceed the amount of memory available in your machine, particularly if the image file is to contain debugging information. For this reason, a temporary disk file is used when all available memory is used by the Watcom Linker.

Normally, the temporary file is created in the default directory. However, by defining the "tmp" environment variable to be a directory, you can tell the Watcom Linker where to create the temporary file. This can be particularly useful if you have a RAM disk. Consider the following definition of the "tmp" environment variable.

```
set tmp=\tmp
```

The Watcom Linker will create the temporary file in the directory "\\tmp".

12 *Watcom Linker Diagnostic Messages*

The Watcom Linker issues three classes of messages; fatal errors, errors and warnings. Each message has a 4-digit number associated with it. Fatal messages start with the digit 3, error messages start with the digit 2, and warning messages start with the digit 1. It is possible for a message to be issued as a warning or an error.

If a fatal error occurs, the linker will terminate immediately and no executable file will be generated.

If an error occurs, the linker will continue to execute so that all possible errors are issued. However, no executable file will be generated since these errors do not permit a proper executable file to be generated.

If a warning occurs, the linker will continue to execute. A warning message is usually informational and does not prevent the creation of a proper executable file. However, all warnings should eventually be corrected.

The messages listed contain references to %s, %S, %a, %x, %d, %l, and %f. They represent strings that are substituted by the Watcom Linker to make the error message more precise.

1. %s represents a string. This may be a segment or group name, or the name of a linker directive or option.
2. %S represents the name of a symbol.
3. %a represents an address. The format of the address depends on the format of the executable file being generated.
4. %x represents a hexadecimal number.
5. %d represents integers in the range -32768 and 32767.
6. %l represents integers in the range -2147483648 and 2147483647.
7. %f represents an executable file format such as DOS, WINDOWS, PHARLAP, NOVELL, OS2, QNX or ELF.

The following is a list of all warning and error messages produced by the Watcom Linker followed by a description of the message. A message may contain more than one reference to "%s". In such a case, the description will reference them as "%sn" where n is the occurrence of "%s" in the message.

MSG 2002 ** internal ** - %s

If this message occurs, you have found a bug in the linker and should report it.

MSG 2008 cannot open %s1 : %s2

An error occurred while trying to open the file "%s1". The reason for the error is given by "%s2". Generally this error message is issued when the linker cannot open a file (e.g., an object file or an executable file).

MSG 3009 dynamic memory exhausted

The linker uses all available memory when linking an application. For DOS-hosted versions of the linker, this includes expanded memory (EMS) and extended memory. When all available memory is used, a spill file will be used. Therefore, unless you are low on disk space, the linker will always be able to generate the executable file. Dynamic memory is the memory the linker uses to build its internal data structures and symbol table. Dynamic memory is the amount of unallocated memory available on your machine (including virtual memory for those operating systems that support it). A spill file is not used for dynamic memory. If the linker issues this message, it cannot link your application. The following are suggestions that may help you in this situation.

1. Concatenate all your object files into one and specify only the resulting object file as input to the linker. For example, if you are linking in a DOS environment, you can issue the following DOS command.

```
C>copy/b *.obj all.obj
```

This technique only works for OMF-type object files. This significantly reduces the size of the file list the linker must maintain.

2. Object files may contain a record which specifies the module name. This information is used by Watcom Debugger to locate modules during a debugging session and usually contains the full path of the source file. This can consume a significant amount of memory when many such object files are being linked. If your source is being compiled by the Watcom C or C++ compiler, you can use the "nm"

option to set the module name to just the file name. This reduces the amount of memory required by the linker. If you are using Watcom Debugger to debug your application, you may have to use the "set source" command so that the source corresponding to a module can be located.

3. Typically, when you are compiling a program for a large code model, each module defines a different "text" segment. If you are compiling your application using the Watcom C or C++ compiler, you can reduce the number of "text" segments that the linker has to process by specifying the "nt" option. The "nt" option allows you to specify the name of the "text" segment so that a group of object files define the same "text" segment.

MSG 2010,3010 I/O error processing %s1 : %s2

An error has occurred while processing the file "%s1". The cause of the error is given by "%s2". This error is usually detected while reading from object and library files or writing to the spill file or executable file. For example, this error would be issued if a "disk full" condition existed.

MSG 2011 invalid object file attribute

The linker encountered an object file that was not of the format required of an object file.

MSG 2012 invalid library file attribute

The linker encountered a library file that was not of the format required of a library file.

MSG 3013 break key detected

The linking process was interrupted by the user from the keyboard.

MSG 1014 stack segment not found

The linker identifies the stack segment by a segment defined as having the "STACK" attribute. This message is issued if no such segment is encountered. This usually happens if the linker cannot find the run-time libraries required to link your application.

MSG 2015 bad relocation type specified

This message is issued if a relocation is found in an object file which the linker does not support.

MSG 2016 %a: absolute target invalid for self-relative relocation

This message is issued, for example, if a near call or jump is made to an external symbol which is defined using the "EQU" assembler directive. "%a" identifies the location of the near call or jump instruction.

MSG 2017 bad location specified for self-relative relocation at %a

This message is issued if a bad fixup is encountered. "%a" defines the location of the fixup.

MSG 2018 relocation offset at %a is out of range

This message is issued when the offset part of a relocation exceeds 64K in a 16-bit executable or an Alpha executable. "%a" defines the location of the fixup. The error is most commonly caused by errors in coding assembly language routines. Consider a module that references an external symbol that is defined in a segment different from the one in which the reference occurred. The module, however, specifies that the segment in which the symbol is defined is the same segment as the segment that references the symbol. This error is most commonly caused when the "EXTRN" assembler directive is placed after the "SEGMENT" assembler directive for the segment referencing the symbol. If the segment that references the symbol is allocated far enough away from the segment that defines the symbol, the linker will issue this message.

MSG 1019 segment relocation at %a

This message is issued when a 16-bit segment relocation is encountered and "FORMAT DOS COM", "FORMAT PHARLAP" or "FORMAT NOVELL" has been specified. None of the above executable file formats allow segment relocation. "%a" identifies the location of the segment relocation.

MSG 2020 size of group %s exceeds 64k by %l bytes

The group "%s" has exceeded the maximum size (64K) allowed for a group in a 16-bit executable by "%l" bytes. Usually, the group is "DGROUP" (the default data segment) and your application has placed too much data in this group. One of the following may solve this problem.

1. If you are using the Watcom C or C++ compiler, you can place some of your data in a far segment by using the "far" keyword when

defining data. You can also decrease the value of the data threshold by using the "zt" compiler option. Any datum whose size exceeds the value of the data threshold will be placed in a far segment.

2. If you are using the Watcom FORTRAN 77 compiler, you can decrease the value of the data threshold by using the "dt" compiler option. Any datum whose size exceeds the value of the data threshold will be placed in a far segment.

MSG 2021 size of segment %s exceeds 64k by %l bytes

The segment "%s" has exceeded the maximum size (64K) for a segment in a 16-bit executable. This usually occurs if you are linking a 16-bit application that has been compiled for a small code model and the size of the application has grown in such a way that the size of the code segment ("_TEXT") has exceeded 64K. You can compile your application for a large code model if you cannot reduce the amount of code in your application.

MSG 2022 cannot have a starting address with an imported symbol

When generating an OS/2 executable file, a symbol imported from a DLL cannot be a start address. When generating a NetWare 386 executable file, a symbol imported from an NLM cannot be a start address.

MSG 1023 no starting address found, using %a

The starting address defines the location where execution is to begin and must be defined by a special "module end" record in one of the object files linked into your application. This message is issued if no such record is encountered in which case a default starting address, namely "%a", will be used. This usually happens if the linker cannot find the run-time libraries required to link your application.

MSG 2026 redefinition of reserved symbol %s

The linker defines certain reserved symbols. These symbols are "_edata", "_end", "__OVLTAB__", "__OVLSTARTVEC__", "__OVLENDVEC__", "__LOVLLDR__", "__NOVLLDR__", "__SOVLLDR__", "__LOVLINIT__", "__NOVLINIT__" and "__SOVLINIT__". The symbols "_edata" and "_end" are defined only if the "DOSSEG" option is specified. Your application must not attempt to define these symbols. "%s" identifies the reserved symbol.

MSG 1027 redefinition of %S ignored

The symbol "%S" has been defined by more than one module; the first definition is used. This is only a warning message. Note that if a symbol is defined more than once and its address is the same in both cases, no warning will be issued. This prevents the warning message from being issued when linking FORTRAN 77 modules that contain common blocks.

MSG 1028,2028 %S is an undefined reference

The symbol "%S" has been referenced but not defined. Check that the spelling of the symbol is consistent. If you wish the linker to ignore undefined references, use the "UNDEFSOK" option.

MSG 2029 premature end of file encountered

This error is issued while processing object files and object modules from libraries and is caused if the end of the file or module is reached before the "module end" record is encountered. The probable cause is a truncated object file.

MSG 2030 multiple starting addresses found

The starting address defines the location where execution is to begin and is defined by a "module end" record in a particular object file. This message is issued if more than one object file contains a "module end" record that defines a starting address.

MSG 2031 segment %s is in group %s and group %s

The segment "%s1" has been defined to be in group "%s2" in one module and in group "%s3" in another module. A segment can only belong to one group.

MSG 1032 record (type 0x%x) not processed

An object record type not supported by the linker has been encountered. This message is issued when linking object modules created by other compilers or assemblers that create object files with records that the linker does not support.

MSG 2033,3033 directive error near '%s'

A syntax error occurred while the linker was processing directives. "%s" specifies where the error occurred.

MSG 2034 %a cannot have an offset with an imported symbol

An imported symbol is one that was specified in an "IMPORT" directive. Imported symbols are defined in Windows or OS/2 16-bit DLLs and in Netware 386 NLMs. References to imported symbols must always have an offset value of 0. If "DosWrite" is an imported symbol, then referencing "DosWrite+2" is illegal. "%a" defines the location of the illegal reference.

MSG 1038 DEBUG directive appears after object files

This message is issued if the first "DEBUG" directive appears after a "FILE" directive. A common error is to specify a "DEBUG" directive after the "FILE" directives in which case no debugging information for those object files is generated in the executable file.

MSG 2039 ALIGNMENT value too small

The value specified in the "ALIGNMENT" option refers to the alignment of segments in the executable file. For 16-bit Windows or 16-bit OS/2, segments in the executable file are pointed to by a segment table. An entry in the segment table contains a 16-bit value which is a multiple of the alignment value. Together they form the offset of the segment from the start of the segment table. The smaller the alignment, the bigger the value required in the segment table to point to the segment. If this value exceeds 64K, then a larger alignment value is required to decrease the size that goes in the segment table.

MSG 2040 ordinal in IMPORT directive not valid

The specified ordinal in the "IMPORT" directive is incorrect (e.g., -1). An ordinal number must be in the range 0 to 65535.

MSG 2041 ordinal in EXPORT directive not valid

The specified ordinal in the "EXPORT" directive is incorrect (e.g., -1). An ordinal number must be in the range 0 to 65535.

MSG 2042 too many IOPL words in EXPORT directive

The maximum number of IOPL words for a 16-bit executable is 63.

MSG 1043 duplicate exported ordinal

This message is issued for ordinal numbers specified in an "EXPORT" directive for symbols belonging to DLLs. This message is issued if an ordinal number is assigned to two different symbols. A warning is issued and the linker assigns a non-used ordinal number to the symbol that caused the warning.

MSG 1044,2044 exported symbol %s not found

This message is issued when generating a DLL or NetWare 386 NLM. An attempt has been made to define an entry point into a DLL or NLM that does not exist.

MSG 1045 segment attribute defined more than once

A segment appearing in a "SEGMENT" directive has been given conflicting or duplicate attributes.

MSG 1046 segment name %s not found

The segment name specified in a "SEGMENT" directive has not been defined.

MSG 1047 class name %s not found

The class name specified in a "SEGMENT" directive has not been defined.

MSG 1048 inconsistent attributes for automatic data segment

This message is issued for Windows or OS/2 16-bit executable files. Two conflicting attributes were specified for the automatic data segment. For example, "LOADONCALL" and "PRELOAD" are conflicting attributes. Only the first attribute is used.

MSG 2049 invalid STUB file

The stub file is not a valid executable file. The stub file is only used for OS/2 executable files and Windows (both Win16 and Win32) executable files.

MSG 1050 invalid DLL specified in OLDLIBRARY option

The DLL specified in an "OLDLIBRARY" option is not a valid dynamic link library.

MSG 2051 STUB file name same as executable file name

When generating an OS/2 or Windows (Win16, Win32) executable file, the stub file name must not be same as the executable file name.

MSG 2052 relocation at %a not in the same segment

This message is only issued for Windows (Win16), OS/2, Phar Lap, and QNX executables. A relative fixup must relocate to the same segment. "%a" defines the location of the fixup.

MSG 2053 %a: cannot reach a DLL with a relative relocation

A reference to a symbol in an OS/2 or Windows 16-bit DLL must not be relative. "%a" defines the location of the reference.

MSG 1054 debugging information incompatible: using line numbers only

An attempt has been made to link an object file with out-of-date debugging information.

MSG 2055 %a: frame must be the same as the target in protected mode

Each relocation consists of three components; the location being relocated, the target (or address being referenced), and the frame (the segment to which the target is adjusted). In protected mode, the segment of the target must be the same as the frame. "%a" defines the location of the fixup. This message does not apply to 32-bit OS/2 and Windows (Win32).

MSG 2056 cannot find library member %s(%s)

Library member "%s2" in library file "%s1" could not be found. This message is issued if the library file could not be found or the library file did not contain the specified member.

MSG 3057 executable format has been established

This message is issued if there is more than one "FORMAT" directive.

MSG 1058 %s option not valid for %s executable

The option "%s1" can only be specified if an executable file whose format is "%s2" is being generated.

MSG 1059,2059 value for %s too large

The value specified for option "%s" exceeds its limit.

MSG 1060 value for %s incorrect

The value specified for option "%s" is not in the allowable range.

MSG 1061 multiple values specified for REALBREAK

The "REALBREAK" option for Phar Lap executables can only be specified once.

MSG 1062 export and import records not valid for %f

This message is issued if a reference to a DLL is encountered and the executable file format is not one that supports DLLs. The file format is represented by "%f".

MSG 2063 invalid relocation for flat memory model at %a

A segment relocation in the flat memory model was encountered. "%a" defines the location of the fixup.

MSG 2064 cannot combine 32-bit segments with 16-bit segments

A 16-bit segment and a 32-bit segment have been encountered. Mixing object files created by a 286 compiler and object files created by a 386 compiler is the most probable cause of this error.

MSG 2065 REALBREAK symbol %s not found

The symbol specified in the "REALBREAK" option for Phar Lap executables has not been defined.

MSG 2066 invalid relative relocation type for an import at %a

This message is issued only if a NetWare 386 executable file is being generated. An imported symbol is one that was specified in an "IMPORT" directive or an import library. Any reference to an imported symbol must not refer to the segment of the imported symbol. "%a" defines the location of the reference.

MSG 2067 %a: cannot relocate between code and data in Novell formats

This message is issued only if a NetWare 386 executable file is being generated. Segment relocation is not permitted. "%a" defines the location of the fixup.

MSG 2068 absolute segment fixup not valid in protected mode

A reference to an absolute location is not allowed in protected mode. A protected-mode application is one that is being generated for OS/2, FlashTek's DOS extender, Phar Lap's 386|DOS-Extender, Tenberry Software's DOS/4G or

DOS/4GW DOS extender, Novell's NetWare 386 operating system, Windows NT, or Windows 95. An absolute location is most commonly defined by the "EQU" assembler directive.

MSG 1069 unload CHECK procedure not found

This message is issued only if a NetWare 386 executable file is being generated. The symbol specified in the "CHECK" option has not been defined.

MSG 2070 START procedure not found

This message is issued only if a NetWare 386 executable file is being generated. The symbol specified in the "START" option has not been defined. The default "START" symbol is "_Prelude".

MSG 2071 EXIT procedure not found

This message is issued only if a NetWare 386 executable file is being generated. The symbol specified in the "EXIT" option has not been defined. The default "STOP" symbol is "_Stop".

MSG 2073 bad Novell file format specified

An invalid NetWare 386 executable file format was specified. Valid formats are NLM, DSK, NAM and LAN.

MSG 2074 circular alias found for %s

An attempt was made to circularly define the symbol name specified in an ALIAS directive. For example:

```
ALIAS foo1=foo2, foo2=foo1
```

MSG 1076 %s option multiply specified

The option "%s" can only be specified once.

MSG 1080 file %s is a %d-bit object file

A 32-bit attribute was encountered while generating a 16-bit executable file format, or a 16-bit attribute was encountered while generating a 32-bit executable file format.

MSG 2082 invalid record type 0x%x

An object record type not recognized by the linker has been encountered. This message is issued when linking object modules created by other compilers or assemblers that create object files with records that the linker does not recognize.

MSG 2083 cannot reference address %a from frame %x

When generating a 16-bit executable, the offset of a referenced symbol was greater than 64K from the location referencing it.

MSG 2084 target offset exceeds 64K at %a

When generating a 16-bit executable, the computed offset for a symbol exceeds 64K. "%a" defines the location of the fixup.

MSG 2086 invalid starting address for .COM file

The value of the segment of the starting address for a 16-bit DOS "COM" file, as specified in the map file, must be 0.

MSG 1087 stack segment ignored in .COM file

A stack segment must not be defined when generating a 16-bit DOS "COM" file. Only a single physical segment is allowed in a DOS "COM" file. The stack is allocated from the high end of the physical segment. That is, the initial value of SP is hexadecimal FFFE.

MSG 3088 virtual memory exhausted

This message is similar to the "dynamic memory exhausted" message. The DOS-hosted version of the linker has run out of memory trying to keep track of virtual memory blocks. Virtual memory blocks are allocated from expanded memory, extended memory and the spill file.

MSG 2089 program too large for a .COM file

The total size of a 16-bit DOS "COM" program must not exceed 64K. That is, the total amount of code and data must be less than 64K since only a single physical segment is allowed in a DOS "COM" file. You must decrease the size of your program or generate a DOS "EXE" file.

MSG 1090 redefinition of %s by %s ignored

The symbol "%s1" has been redefined by module "%s2". This message is issued when the size specified in the "NAMELEN" option has caused two symbols to map to the same symbol. For example, if the symbols *routine1* and *routine2* are encountered and "OPTION NAMELEN=7" is specified, then this message will be issued since the first seven characters of the two symbols are identical.

MSG 2092 NEWSEGMENT directive appears before object files

The 16-bit "NEWSEGMENT" directive must appear after a "FILE" directive.

MSG 2093 cannot open %s

This message is issued when the linker is unable to open a file and is unable to determine the cause.

MSG 2094 i/o error processing %s

This message is issued when the linker has encountered an i/o error while processing the file and is unable to determine the cause. This message may be issued when reading from object and library files, or writing to the executable and spill file.

MSG 1098 Offset option must be a multiple of %dK

The value specified with the "OFFSET" option must be a multiple of 4K (4096) for Phar Lap and QNX executables and a multiple of 64K (65536) for OS/2 and Windows 32-bit executables.

MSG 2099 symbol name too long: %s

The maximum size (approximately 2048) of a symbol has been exceeded. Reduce the size of the symbol to avoid this error.

MSG 1101 invalid incremental information file

The incremental information file is corrupt or from an older version of the compiler. The old information file and the executable will be deleted and new ones will be generated.

MSG 1102 object file %s not found for tracing

A "SYMTRACE" or "MODTRACE" directive contained an object file (namely %s) that could not be found.

MSG 1103 library module %s(%s) not found for tracing

A "SYMTRACE" or "MODTRACE" directive contained an object module (namely module %s1 in library %s2) that could not be found.

MSG 1107 undefined system name: %s

The name %s was referenced in a "SYSTEM" directive but never defined by a system block definition.

MSG 1108 system %s defined more than once

The name %s has appeared in a system definition block more than once.

MSG 1109 OFFSET option is less than the stack size

For the QNX operating system, the stack is placed at the front of the executable image and thus the initial load address must leave enough room for the stack.

MSG 1110 library members not allowed in libfile

Only object files are allowed in a "LIBFILE" directive. This message will be issued if a module from a library file is specified in a "LIBFILE" directive.

MSG 1111 error in default system block

The default system block definition (system name "286" for 16-bit applications) and (system name "386" for 32-bit applications) contains a directive error. The system name "286" or "386" is automatically referenced by the linker when the format of the executable cannot be determined (i.e. no "FORMAT" directive has been specified).

MSG 3114 environment name specified incorrectly

This message is specified if the environment variable is not properly enclosed between two percent (%) characters.

MSG 1115 environment name %s not found

The environment variable %s has not been defined in the environment space.

MSG 1117 segment number too high for a movable entry point

The segment number of a moveable segment must not exceed 255 for 16-bit executables. Reduce the number of segments or use the "PACKCODE" option.

MSG 1118 heap size too large

This message is issued if the size of the heap, stack and the default data segment (group DGROUP) exceeds 64K for 16-bit executables.

MSG 2119 wlib import statement incorrect

The "EXPORT" directive allows you to specify a library command file. This command file is scanned for any librarian commands that create import library entries. An invalid command was detected. See the section entitled "The EXPORT Directive" for the correct format of these commands.

MSG 2120 application too large to run under DOS

This message is issued if the size of the 16-bit DOS application exceeds 1M.

MSG 1121 '%s' has already been exported

The linker has detected an attempt to export a symbol more than once. For example, a name appearing in more than one "EXPORT" directive will cause this message to be issued. Also, if you have declared a symbol as an export in your source and have also specified the same symbol in an "EXPORT" directive, this message will be issued. This message is only a warning.

MSG 3122 no FILE directives found

This message is issued if no "FILE" directive has been specified. In other words, you have specified no object files to link.

MSG 3123 overlays are not supported in this version of the linker

This version of the linker does not support the creation of overlaid 16-bit executables.

MSG 1124 lazy reference for %S has different default resolutions

A lazy external reference is one which has two resolutions: a preferred one and a default one which is used if the preferred one is not found. In this case, the

linker has found two lazy references that have the same preferred resolution but different default resolutions.

MSG 1125 multiple aliases found for %S

The linker has found a name which has been aliased to two different symbols.

MSG 1126 %s has been modified: doing full relink

The linker has determined that the time stamps on the executable file and symbolic information file (.sym) are different. An incremental link will not be done.

MSG 2127 cannot export symbol %S

An attempt was made to export a symbol defined with an absolute address or to export an imported symbol. It is not possible to export these symbols with the "EXPORT" directive.

MSG 3128 directive error near beginning of input

The linker detected an error at the start of the command line.

MSG 3129 address information too large

The linker has encountered a segment that appears in more than 11000 object files. An empty segment does not affect this limit. This can only occur with WATCOM debugging information. If this message appears, switch to DWARF debugging information.

MSG 1130 %s is an invalid shared nlm file

The NLM specified in a "SHAREDNLM" option is not valid.

MSG 3131 cannot open spill file: file already exists

All 26 of the DOS-hosted linker's possible spill file names are in use. Spill files can accumulate when linking on a multi-tasking system and the directory in which the spill file is created is identical for each invocation of the linker.

MSG 2132 curly brace delimited list incorrect

A list delimited by curly braces is not correct. The most likely cause is a missing right brace.

MSG 1133 no realbreak specified for 16-bit code

While generating a Phar Lap executable file, both 16-bit and 32-bit code was linked together and no "REALBREAK" option has been specified. A warning message is issued since this may be a potential problem.

MSG 1134 %s is an invalid message file

The file specified in a "MESSAGE" option for NetWare 386 executable files is invalid.

MSG 1136 relocation to a read/write data segment found at %a

The "RWRELOCHECK" option for 16-bit Windows (Win16) executables has been specified and the linker has detected a segment relocation to a read/write data segment.

MSG 3137 too many errors encountered

This message is issued when the number of error messages issued by the linker exceeds the number specified by the "MAXERRORS" option.

MSG 3138 invalid filename '%s'

The linker performs a simple filename validation whenever a filename is specified to the linker. For example, a directory specification is not a valid filename.

MSG 3139 cannot have both 16-bit and 32-bit object files

It is impossible to mix 16-bit code and 32-bit code in the same executable when generating a QNX executable file.

MSG 1140 invalid message number

An invalid message number has been specified in a "DISABLE" directive.

MSG 1141 virtual function table record for %s mismatched

The linker performs a consistency check to ensure that the C++ compiler has not generated incorrect virtual function information. If the message is issued, please report this problem.

MSG 1143 not enough memory to sort map file symbols

There was not enough memory for the linker to sort the symbols in the "Memory Map" portion of the map file. This will only occur when the "SORT GLOBAL" option has been specified.

MSG 1145 %S is both pure virtual and non-pure virtual

A function has been declared both as "pure" and "non-pure" virtual.

MSG 2146 %s is an invalid object file

Something was encountered in the object file that cannot be processed by the linker.

MSG 3147 Ambiguous format specified

Not enough of the FORMAT directive attributes were specified to enable the linker to determine the executable file format. For example,

```
FORMAT OS2
```

will generate this message.

MSG 1148 Invalid segment type specified

The segment type must be one of CODE or DATA.

MSG 1149 Only one debugging format can be specified

The debugging format must be one of WATCOM, Codeview, Dwarf (default), or Novell. You cannot specify multiple debugging formats.

MSG 1150 file %s has code for a different processor

An object file has been encountered which contains code compiled for a different processor (e.g., an Intel application and an Alpha object file).

MSG 2151 big endian code not supported

Big endian code is not supported by the linker.

MSG 2152 no dictionary found

No symbol search dictionary was found in a library that the linker attempted to process.

MSG 2154 cannot execute %s1 : %s2

An attempt by the linker to spawn another application failed. The application is specified by "%s1" and the reason for the failure is specified by "%s2".

MSG 2155 relocation at %a to an improperly aligned target

Some relocations in Alpha executables require that the object be aligned on a 4 byte boundary.

MSG 2156 OPTION INCREMENTAL must be one of the first directives specified

The option must be specified before any option or directive which modifies the linker's symbol table (e.g., IMPORT, EXPORT, REFERENCE, ALIAS).

MSG 3157 no code or data present

The linker requires that there be at least 1 byte of either code or data in the executable.

MSG 1158 problem adding resource information

The resource file is invalid or corrupt.

MSG 3159 incremental linking only supports DWARF debugging information

When OPTION INCREMENTAL is used, you cannot specify non-Dwarf debugging information for the executable. You must specify DEBUG DWARF when requesting debugging information.

MSG 3160 incremental linking does not support dead code elimination

When OPTION INCREMENTAL is used, you cannot specify OPTION ELIMINATE.

MSG 1162 relocations on iterated data not supported

An object file was encountered that contained an iterated data record that requires relocation. This is most commonly caused by a module coded in assembly language.

MSG 1163 module has not been compiled with the "zv" option

When OPTION VFREMOVAL is used, all object files must be compiled with the "zv" option. The linker has detected an object file that has not been compiled with this option.

MSG 3164 incremental linking does not support virtual function removal

When OPTION INCREMENTAL is used, you cannot also specify OPTION VFREMOVAL.

MSG 1165 resource file %s too big

The resource file specified in OPTION RESOURCE was too big to fit inside the QNX executable. The maximum size is approximately 32000 bytes.

MSG 2166 both %s1 and %s2 marked as starting symbols

If the linker sees that there is more than one starting address specified in the program and they have symbol names associated with them, it will emit this error message. If there is more than one starting address specified and at least one of them is unnamed, it will issue message 2030.

#

directive 30

1

16-bit DOS .COM 8
 16-bit DOS executables 8
 16-bit executables 8
 16-bit OS/2 DLLs 9
 16-bit OS/2 executables 9
 16-bit QNX executables 9
 16-bit Windows 3.x DLLs 10
 16-bit Windows 3.x executables 10

3

32-bit AutoCAD ADI executables 11
 32-bit AutoCAD ADS executables 11
 32-bit DOS/4GW executables 12
 32-bit executables 11
 32-bit FlashTek executables 12
 32-bit Netware NLMs 13
 32-bit OS/2 DLLs 14
 32-bit OS/2 executables 13
 32-bit OS/2 PM executables 14
 32-bit Phar Lap executables 14
 32-bit QNX executables 15
 32-bit TNT executables 15
 32-bit Win NT character-mode executables 17
 32-bit Win NT DLLs 17
 32-bit Win NT windowed executables 17
 32-bit Windows 3.x DLLs 16

32-bit Windows 3.x executables 15
 32-bit Windows 95 DLLs 16
 32-bit Windows 95 executables 16
 386|DOS-Extender 191

A

ALIAS directive 22
 ALIGNMENT option 23
 ANONYMOUSEXPORT directive 24
 apostrophes 21, 68
 applications
 creating for 16-bit OS/2 181
 creating for 32-bit OS/2 181
 creating for 32-bit Windows 207
 creating for DOS 165
 creating for DOS/4G 181
 creating for ELF 171
 creating for FlashTek 181
 creating for NetWare 386 175
 creating for Phar Lap 286|Dos-Extender 181
 creating for Phar Lap 386|Dos-Extender 189
 creating for QNX 195
 creating for Win32 207
 creating for Windows 3.x 199
 creating for Windows NT 207
 AR-format 3
 ARTIFICIAL option 26

B

blanks in file names 21

C

CACHE option 27
CALLBUFS runtime option 134
CASEEXACT option 28
CHECK option 29
Codeview 34
COFF 3
command line format
 WLINK 5, 165, 171, 175, 181, 189, 195, 199,
 207
comment (#) directive 30
COMMIT directive 31
Compactor 34
CONSOLE runtime option 132
COPYRIGHT option 32
CUSTOM option 33
CV4 34
CVPACK 34-35
CVPACK option 34

D

DBCS
 Chinese 77
 Japanese 77
 Korean 77
dead code elimination 47, 129, 142
DEBUG directive 35
DEBUG options
 ALL 36
 CODEVIEW 35
 DWARF 35
 LINES 36
 LOCALS 36
 NOVELL 36
 ONLYEXPORTS 36-37, 40

 REFERENCED 37
 TYPES 36
 WATCOM 35
debugging information
 all 39
 for NetWare 386 debugger 39
 global symbol 36, 39
 line numbering 36-37
 local symbol 36, 38
 NetWare 386 global symbol 36
 strip from "EXE" file 41
 typing 36, 38
Debugging Information Compactor 34-35
default directive file 7, 19, 28, 155
 wlink.lnk 28
DESCRIPTION option 42
directives 19
 # 30
 ALIAS 22
 ANONYMOUSEXPORT 24
 comment 30
 COMMIT 31
 DEBUG 35
 DISABLE 43
 ENDLINK 48
 EXPORT 50
 FILE 54
 FORMAT 56
 IMPORT 68
 include 71
 LANGUAGE 77
 LIBFILE 78
 LIBPATH 80
 LIBRARY 82
 MODFILE 95
 MODTRACE 96
 MODULE 97
 NAME 99
 NEWSEGMENT 102
 OPTION 114
 OPTLIB 115
 PATH 122
 REFERENCE 129
 RUNTIME 132

SEGMENT 138
 SORT 143
 STARTLINK 146
 SYMTRACE 151
 SYSTEM 153
 DISABLE directive 43
 DOS applications
 creating 165
 DOS/4G applications
 creating 181
 DOSSEG option 45
 DOSSTYLE runtime option 133

E

_edata linker symbol 46
 ELF 3
 ELF applications
 creating 171
 ELIMINATE option 47
 _end linker symbol 46
 ENDLINK directive 48
 environment variables
 LIB 83, 105, 116
 LIBDIR 19
 PATH 7, 19, 28, 148, 155
 tmp 168, 174, 179, 186, 193, 205, 212
 TMPDIR 198
 WATCOM 7, 19, 28, 155
 errors 43, 213
 executable formats 3
 EXIT option 49
 __export 52
 EXPORT directive 50

F

fatal errors 43, 213
 FILE directive 54
 FlashTek applications
 creating 181
 FORMAT directive 56

G

general directives/options 19

H

HEAPSIZE option 64
 HELP option 65
 host 4
 host operating system 4

I

IMPFILE option 66
 IMPLIB option 67
 import definitions 184, 203, 210
 IMPORT directive 68
 import library 66-67, 185, 204, 211
 import library command file 66
 include directive 71
 incremental linking 74

INCREMENTAL option 74
Intel OMF 3
internal relocation 76, 158
INTERNALRELOCS option 76
invoking Watcom Linker 5, 165, 171, 175, 181,
189, 195, 199, 207
ISTKSIZE runtime option 134

L

LANGUAGE directive 77
LANGUAGE options
 CHINESE 77
 JAPANESE 77
 KOREAN 77
LIB environment variable 83, 105, 116
LIBDIR environment variable 19
LIBFILE directive 78
LIBPATH directive 80
LIBRARY directive 82
library file 66-67
LINEARRELOCS option 85
linker symbols
 _edata 46
 _end 46
linking notation 20
LONGLIVED option 86

M

mangled names in C++ 87, 143
MANGLEDNAMES option 87
MANYAUTODATA option 88
map file 89
MAP option 89
MAXDATA option 90

MAXERRORS option 91
MAXIBUF runtime option 134
MAXREAL runtime option 133
memory layout 45, 167, 173, 178, 185, 192, 197,
204, 211
memory requirements 168, 174, 179, 186, 193,
198, 205, 212
message
 1014 215
 1019 216
 1023 217
 1027 217
 1028,2028 218
 1032 218
 1038 219
 1043 219
 1044,2044 220
 1045 220
 1046 220
 1047 220
 1048 220
 1050 220
 1054 221
 1058 221
 1059,2059 221
 1060 221
 1061 222
 1062 222
 1069 223
 1076 223
 1080 223
 1087 224
 1090 225
 1098 225
 1101 225
 1102 225
 1103 226
 1107 226
 1108 226
 1109 226
 1110 226
 1111 226
 1115 226
 1117 227

1118	227	2052	220
1121	227	2053	221
1124	227	2055	221
1125	228	2056	221
1126	228	2063	222
1130	228	2064	222
1133	229	2065	222
1134	229	2066	222
1136	229	2067	222
1140	229	2068	222
1141	229	2070	223
1143	230	2071	223
1145	230	2073	223
1148	230	2074	223
1149	230	2082	224
1150	230	2083	224
1158	231	2084	224
1162	231	2086	224
1163	232	2089	224
1165	232	2092	225
2002	214	2093	225
2008	214	2094	225
2010,3010	215	2099	225
2011	215	2119	227
2012	215	2120	227
2015	215	2127	228
2016	216	2132	228
2017	216	2146	230
2018	216	2151	230
2020	216	2152	230
2021	217	2154	231
2022	217	2155	231
2026	217	2156	231
2029	218	2166	232
2030	218	3009	214
2031	218	3013	215
2033,3033	218	3057	221
2034	218	3088	224
2039	219	3114	226
2040	219	3122	227
2041	219	3123	227
2042	219	3128	228
2049	220	3129	228
2051	220	3131	228

3137 229
3138 229
3139 229
3147 230
3157 231
3159 231
3160 231
3164 232
MESSAGES option 92
Microsoft OMF 3
MINDATA option 93
MINIBUF runtime option 134
MINREAL runtime option 133
MODFILE directive 95
MODNAME option 94
MODTRACE directive 96
MODULE directive 97
MS2WLINK command 168, 187, 205
MULTILOAD option 98

N

NAME directive 99
NAMELEN option 100
NATIVE runtime option 132
NetWare 386 applications
 creating 175
NetWare 386 debugger 39
NEWFILES option 101
NEWSEGMENT directive 102
NISTACK runtime option 134
NLMFLAGS option 103
NOAUTODATA option 104
NODEFAULTLIBS option 105
NOREDEFSOK option 127
NORELOCS option 106
NOSTDCALL option 107
notation 20
NOUNDEFSOK option 159

O

OBJALIGN option 108
OFFSET option 110
OLDLIBRARY option 109
OMF 3
OMF library 3
ONEAUTODATA option 113
operating system
 host 4
OPTION directive 114
options
 ALIGNMENT 23
 ARTIFICIAL 26
 CACHE 27
 CASEEXACT 28
 CHECK 29
 COPYRIGHT 32
 CUSTOM 33
 CVPACK 34
 DESCRIPTION 42
 DOSSEG 45
 ELIMINATE 47
 EXIT 49
 HEAPSIZE 64
 HELP 65
 IMPFIL 66
 IMPLIB 67
 INCREMENTAL 74
 INTERNALRELOCS 76
 LINEARRELOCS 85
 LONGLIVED 86
 MANGLEDNAMES 87
 MANYAUTODATA 88
 MAP 89
 MAXDATA 90
 MAXERRORS 91
 MESSAGES 92
 MINDATA 93
 MODNAME 94

MULTILOAD 98
 NAMELEN 100
 NEWFILES 101
 NLMFLAGS 103
 NOAUTODATA 104
 NODEFAULTLIBS 105
 NOREDEFSOK 127
 NORELOCS 106
 NOSTDCALL 107
 NOUNDEFSOK 159
 OBJALIGN 108
 OFFSET 110
 OLDLIBRARY 109
 ONEAUTODATA 113
 OSDOMAIN 117
 OSNAME 119
 PACKCODE 120
 PACKDATA 121
 PRIVILEGE 124
 PROTMODE 125
 PSEUDOPREEMPTION 118
 QUIET 126
 REDEFSOK 127
 REENTRANT 128
 RESOURCE 130
 RWRELOCHECK 136
 SCREENNAME 137
 SHARELIB 141
 SHOWDEAD 142
 STACK 144
 START 145
 STATICS 147
 STUB 148
 SYMFILE 149
 SYNCHRONIZE 152
 THREADNAME 157
 TOGGLERELOCS 158
 UNDEFSOK 159
 VERBOSE 160
 VERSION 161
 VFREMOVAL 162
 XDCDATA 163
 OPTLIB directive 115
 OS/2 16-bit applications

creating 181
 OS/2 32-bit applications
 creating 181
 OS/2 Dynamic Link Libraries 184
 OS/2 program modules 184
 OS2 runtime option 132
 OSDOMAIN option 117
 OSNAME option 119

P

PACKCODE option 120
 PACKDATA option 121
 PATH directive 122
 PATH environment variable 7, 19, 28, 148, 155
 PE format executable 58
 Phar Lap 286|Dos-Extender applications
 creating 181
 Phar Lap 386|Dos-Extender applications
 creating 189
 Phar Lap OMF-386 3
 Phar Lap TNT 58
 PL format executable 58
 POSIX runtime option 132
 privilege
 ring 0 135
 ring 3 135
 PRIVILEGE option 124
 PRIVILEGED runtime option 135
 PROTMODE option 125
 PSEUDOPREEMPTION option 118
 punctuation characters 21

Q

QNX applications

creating 195
QUIET option 126

R

REALBREAK runtime option 134
REDEFSSOK option 127
REENTRANT option 128
REFERENCE directive 129
relocation
 internal 76, 158
resource file 130
RESOURCE option 130
response files
 conversion 168, 187, 205
ring 0 135
ring 3 135
running in 32-bit protected mode 191
RUNTIME directive 132
RUNTIME options
 CALLBUFS 134
 CONSOLE 132
 DOSSTYLE 133
 ISTKSIZE 134
 MAXIBUF 134
 MAXREAL 133
 MINIBUF 134
 MINREAL 133
 NATIVE 132
 NISTACK 134
 OS2 132
 POSIX 132
 PRIVILEGED 135
 REALBREAK 134
 UNPRIVILEGED 135
 version 132
 WINDOWS 132
runtime version option 132
RWRELOCHECK option 136

S

SCREENNAME option 137
SEGMENT directive 138
segment ordering 45, 167, 173, 178, 185, 192,
 197, 204, 211
SHARELIB option 141
SHOWDEAD option 142
SORT directive 143
space character 21
special characters 21
STACK option 144
START option 145
STARTLINK directive 146
STATICS option 147
__stdcall 107
STUB option 148
symbol file 149
SYMFILE option 149
SYMTRACE directive 151
SYNCHRONIZE option 152
SYSTEM directive 5, 153
system name 153

T

THREADNAME option 157
tmp environment variable 168, 174, 179, 186,
 193, 205, 212
TMPDIR environment variable 198
TNT DOS extender 58
TOGGLERELOCS option 158

U

UNDEFSOK option 159
 UNPRIVILEGED runtime option 135
 USE16 segments 192
 usemsg 131
 using environment variables in directives 19

V

VERBOSE option 160
 VERSION option 161
 VFREMOVAL option 162
 virtual functions 142, 162

W

warnings 43, 213
 Watcom C/C++ options
 zm 47
 WATCOM environment variable 7, 19, 28, 155
 Win16 applications
 creating 199
 Win16 Dynamic Link Libraries 202
 Win16 program modules 202
 Win32 applications
 creating 207
 Win32 Dynamic Link Libraries 209
 Win32 program modules 209
 window function 50, 72
 Windows 3.x applications
 creating 199
 Windows 32-bit applications

 creating 207
 Windows NT applications
 creating 207
 WINDOWS runtime option 132
 WLINK
 command line format 5, 165, 171, 175, 181,
 189, 195, 199, 207
 WLINK command line
 invoking WLINK 5, 165, 171, 175, 181, 189,
 195, 199, 207
 WLINK notation 20
 wlink.lnk
 default directive file 7, 19, 28, 155
 wsystem.lnk
 directive file 7, 19, 28, 155
 WSTRIP 39, 41
 WSTRIP command 41

X

x32r 12
 x32rv 12
 XDCDATA option 163

Z

zm compiler option (Watcom C/C++) 47